
Anaconda Platform Documentation

Release 5.4.1

Anaconda Inc.

Mar 04, 2021


Contents

1	Installing Anaconda Enterprise	3
2	Administering Anaconda Enterprise	45
3	Using Anaconda Enterprise	137
4	Troubleshooting	227
5	Reference materials	233

Anaconda Enterprise is an enterprise-ready, secure and scalable data science platform that empowers teams to govern data science assets, collaborate and deploy their data science projects.

With Anaconda Enterprise, you can do the following:

- **Develop:** ML/AI pipelines in a central development environment that scales from laptops to thousands of nodes
- **Govern:** Complete reproducibility from laptop to cluster with the ability to configure access control
- **Automate:** Model training and deployment on scalable, container-based infrastructure



Installing Anaconda Enterprise

When you initially install Anaconda Enterprise, you can install it on one to five nodes. You are not bound to that initial configuration, however. After completing the installation, you can *add or remove nodes* on the cluster as needed, including GPUs.

When you've determined an initial topology for your cluster, follow this high-level process to install Anaconda Enterprise:



1.1 Installation requirements

For your Anaconda Enterprise installation to complete successfully, your systems must meet the requirements outlined below. The installation requirements for Anaconda Enterprise are the same whether you choose to install the platform on-premises, hosted VSphere, or on a cloud server. There are cloud-specific requirements related to performance, however, so ensure your chosen cloud platform meets *the minimum specifications outlined here* before you begin.

The installer performs pre-flight checks, and only allows installation to continue on nodes that are configured correctly, and include the required kernel modules. If you want to perform the system check yourself, before installation, you

can *run the command* on your intended master and worker nodes *after you download and extract the installer*.

When you initially install Anaconda Enterprise, you can install the cluster on one to five nodes. You are not bound to that initial configuration, however. **After completing the installation, you can add or remove nodes on the cluster as needed.** For more information, see *Adding and removing nodes*.

A rule of thumb for determining how to size your system is 1 CPU, 1GB of RAM and 5 GB of disk space for each project session or deployment. For more information about sizing for a particular component, see the following minimum requirements:

- *Hardware requirements*
- *Disk IOPS requirements*
- *Storage and memory requirements*
- *Operating system requirements*
- *Security requirements*
- *Kernel module requirements*
- *System control settings*
- *GPU requirements*
- *Network requirements*
- *TLS/SSL certificate requirements*
- *DNS requirements*
- *Browser requirements*

To use Anaconda Enterprise with a cloud platform, refer to *Cloud performance requirements* for cloud-specific performance requirements.

To use Spark Hadoop data sources with Anaconda Enterprise, refer to *Installing Livy server for Hadoop Spark access* and *Configuring Livy server for Hadoop Spark access*.

To verify your systems meet the requirements, see *Verifying system requirements*.

Hardware requirements

The following are minimum specifications for the master and worker nodes, as well as the entire cluster.

Note: We recommend having 1 master and 1 worker **per cluster**.

Master node	Minimum
CPU	16 cores
RAM	64GB
Disk space in /opt/anaconda	500GB*
Disk space in /var/lib/gravity	300GB**
Disk space in /tmp or \$TMPDIR	50GB

Worker nodes	Minimum
CPU	16 cores
RAM	64GB
Disk space in /var/lib/gravity	300GB
Disk space in /tmp or \$TMPDIR	50GB

*NOTES regarding the minimum disk space in /opt/anaconda:

- This total includes project and package storage (including mirrored packages).
- Currently /opt and /opt/anaconda **must** be an ext4 or xfs filesystem, and **cannot** be an NFS mount-point. Subdirectories of /opt/anaconda may be mounted through NFS. See [Mounting an NFS share](#) for more information.
- If you are installing Anaconda Enterprise on an xfs filesystem, it needs to support d_type to work properly. If your XFS filesystem has been formatted with the -n ftype=0 option, it won't support d_type, and will therefore need to be recreated using a command similar to the following before installing Anaconda Enterprise:

```
mkfs.xfs -n ftype=1 /path/to/your/device
```

**NOTES regarding the minimum disk space in /var/lib/gravity:

- This volume **MUST be mounted on local storage**. Core components of Kubernetes run from this directory, some of which are extremely intolerant of disk latency. Network-Attached Storage (NAS) and Storage Area Network (SAN) solutions are susceptible to latency, and are therefore not supported.
- This total includes additional space to accommodate upgrades, and is recommended to have available during installation as it can be difficult to add space after the fact.
- We **strongly recommend** that you set up the /opt/anaconda and /var/lib/gravity partitions using Logical Volume Management (LVM), to provide the flexibility needed to accommodate easier future expansion.

To check the number of cores, run `nproc`.

Disk IOPS requirements

Master and worker nodes require a minimum of 3000 *concurrent* input/output operations per second (IOPS)—fewer than 3000 concurrent IOPS will fail. Cloud providers report concurrent disk IOPS.

Hard disk manufacturers report *sequential* IOPS, which are different than concurrent IOPS. On-premises installations require servers with disks that support a minimum of 50 sequential IOPS. We recommend using SSD or better.

Storage and memory requirements

Approximately 50GB of available free space on each node is required for the Anaconda Enterprise installer to temporarily decompress files to the `/tmp` directory during the installation process.

If adequate free space is not available in the `/tmp` directory, you can specify the location of the temporary directory to be used during installation by setting the `TMPDIR` environment variable to a different location.

EXAMPLE:

```
sudo TMPDIR=/tmp2 ./gravity install
```

Note: When using `sudo` to install, the temporary directory must be set explicitly in the command line to preserve `TMPDIR`. The master node and each worker node all require a temporary directory of the same size, and should each use the `TMPDIR` variable as needed.

To check your available disk space, use the built-in Linux `df` utility with the `-h` parameter for human readable format:

```
df -h /var/lib/gravity
df -h /opt/anaconda
df -h /tmp
# or
df -h $TMPDIR
```

To show the free memory size in GB, run:

```
free -g
```

Operating system requirements

- Anaconda Enterprise cannot be installed with heterogeneous versions in the same cluster. Before installing, *verify that all cluster nodes are operating the same version of the OS.*

Anaconda Enterprise currently supports the following Linux versions:

- RHEL/CentOS 7.2, 7.3, 7.4, 7.5, 7.6, 7.7, 7.8, 8.0
- Ubuntu 16.04
- SUSE 12 SP2, 12 SP3 **Requirement:** Set `DefaultTasksMax=infinity` in `/etc/systemd/system.conf`.

To find your operating system version run `cat /etc/*release*` or `lsb-release -a`.

- Optionally create a new directory and set `TMPDIR`. User 1000 (or the UID for the service account) needs to be able to write to this directory. This means they can read, write and execute on the `$TMPDIR`.

For example, to give write access to UID 1000, run the following command:

```
sudo chown 1000 -R $TMPDIR
```

Note: When installing Anaconda Enterprise on a system with multiple nodes, verify that the clock of each node is in sync with the others prior to starting the installation process, to avoid potential issues. We recommend using the Network Time Protocol (NTP) to synchronize computer system clocks automatically over a network. See instructions [here](#).

Security requirements

- Verify you have `sudo` access.
- Make sure that the firewall is permanently set to keep the required ports open, and will save these settings across reboots. Then restart the firewall to load these settings immediately.

Various tools may be used to configure firewalls and open required ports, including `iptables`, `firewall-cmd`, `susefirewall2`, and others.

For all CentOS and RHEL nodes:

- Ensure that SELinux is not in enforcing mode, by either disabling it or putting it in permissive mode in the `/etc/selinux/config` file.

After rebooting, run the following command to verify that SELinux is not being enforced:

```
~]~ getenforce
```

The result should be either `Disabled` or `Permissive`.

Kernel module requirements

The Anaconda Enterprise installer checks to see if the following modules required for Kubernetes to function properly are present, and alerts you if any are not loaded:

Linux Distribution	Version Modules	
CentOS	7.2	bridge, ebtables, iptable_filter, overlay
RedHat Linux	7.2	bridge, ebtables, iptable_filter
CentOS	7.3, 7.4, 7.5, 7.6, 7.7, 8.0	br_netfilter, ebtables, iptable_filter, overlay
RedHat Linux	7.3, 7.4, 7.5, 7.6, 7.7, 8.0	br_netfilter, ebtables, iptable_filter, overlay
Ubuntu	16.04	br_netfilter, ebtables, ebtable_filter, iptable_filter, overlay
Suse	12 SP2, 12 SP3	br_netfilter, ebtables, iptable_filter, overlay

Module name	Purpose
bridge	Required for Kubernetes iptables-based proxy to work correctly
br_netfilter	Required for Kubernetes iptables-based proxy to work correctly
overlay	Required to use overlay or overlay2 Docker storage driver
ebtables	Required to allow a service to communicate back to itself via internal load balancing when necessary
iptable_filter	Required to make sure that the firewall rules that Kubernetes sets up function properly
iptable_nat	Required to make sure that the firewall rules that Kubernetes sets up function properly

To check if a particular module is loaded, run the following command:

```
lsmod | grep <module_name>
```

If the command doesn't produce any result, the module is not loaded.

Run the following command to load the module:

```
sudo modprobe <module_name>
```

If your system does not load modules at boot, run the following—for each module—to ensure they are loaded upon reboot:

```
sudo echo -e '<module_name>' > /etc/modules-load.d/<module_name>.conf
```

System control settings

Anaconda Enterprise requires the following `sysctl` settings to function properly:

System setting	Purpose
net.bridge.bridge-nf-call-iptables	Works with bridge kernel module to ensure Kubernetes iptables-based proxy works correctly
net.bridge.bridge-nf-call-ip6tables	Works with bridge kernel module to ensure Kubernetes iptables-based proxy works correctly
fs.may_detach_mounts	Can cause conflicts with the docker daemon, and leave pods in stuck state if not enabled
net.ipv4.ip_forward	Required for internal load balancing between servers to work properly
fs.inotify.max_user_watches	Set to 1048576 to improve cluster longevity

Run the following commands to set system control settings:

```
sudo sysctl -w <system_setting>=1
```

To persist system settings on boot, run the following for each setting:

```
sudo echo -e "<system_setting> = 1" > /etc/sysctl.d/10-<system_setting>.conf
```

Verifying system requirements

Anaconda Enterprise performs system checks during the install to verify CPU, RAM and other system requirements. The system checks can also be performed manually before the installation using the following commands from the installer directory, `~/anaconda-enterprise-<installer-version>`.

Note: You can perform this check after downloading and extracting the installer.

To perform system checks on a *master* node, run the following command as `sudo` or `root` user:


```
sudo ./gravity check --profile ae-master
```

To perform system checks on a *worker* node, run the following command as sudo or root user:

```
sudo ./gravity check --profile ae-worker
```

If all of the system checks pass and all requirements are met, the output from the above commands will be empty. If the system checks fail and some requirements are not met, the output will indicate which system checks failed.

GPU requirements

To use GPUs with Anaconda Enterprise, you'll need to install version 9.2 or 10.0 of the NVIDIA CUDA driver *on the host operating system of any GPU worker nodes*. You can install the drivers using the package manager or the [Nvidia runfile](#) or by using `rpm (local)` or `rpm (network)` for SLES, CentOS, and RHEL, and `deb (local)` or `deb (network)` for Ubuntu.

GPU deployments should use one of the following models:

- Tesla V100 (recommended)
- Tesla P100 (adequate)

Network requirements

Anaconda Enterprise requires the following network ports to be **externally accessible**:

Port	Protocol	Description
80	TCP	Anaconda Enterprise UI (plaintext)
443	TCP	Anaconda Enterprise UI (encrypted)
32009	TCP	Operations Center Admin UI

These ports need to be externally accessible **during installation only**, and can be closed after completing the install process:

Port	Protocol	Description
4242	TCP	Bandwidth checker utility
61009	TCP	Install wizard UI access required during cluster installation
61008, 61010, 61022-61024	TCP	Installer agent ports

The following ports are used for cluster operation, and therefore **must be open internally, between cluster nodes**:

Port	Protocol	Description
53	TCP and UDP	Internal cluster DNS
2379, 2380, 4001, 7001	TCP	Etd server communication
3008-3012	TCP	Internal Anaconda Enterprise service
3022-3025	TCP	Teleport internal SSH control panel
3080	TCP	Teleport Web UI
5000	TCP	Docker registry
6443	TCP	Kubernetes API Server
6990	TCP	Internal Anaconda Enterprise service
7496, 7373	TCP	Peer-to-peer health check
7575	TCP	Cluster status gRPC API
8081, 8086-8091, 8095	TCP	Internal Anaconda Enterprise service
8472	UDP	Overlay network
9080, 9090, 9091	TCP	Internal Anaconda Enterprise service
10248-10250, 10255	TCP	Kubernetes components
30000-32767	TCP	Kubernetes internal services range

You'll also need to **update your firewall settings** to ensure that the `10.244.0.0/16` pod subnet and `10.100.0.0/16` service subnet are accessible to every node in the cluster, and grant all nodes the ability to communicate via their primary interface.

For example, if you're using iptables:

```
iptables -A INPUT -s 10.244.0.0/16 -j ACCEPT
iptables -A INPUT -s 10.100.0.0/16 -j ACCEPT
iptables -A INPUT -s <node_ip> -j ACCEPT
```

Where `<node_ip>` specifies the internal IP address(es) used by all nodes in the cluster to connect to the AE5 master.

If you plan to use online package mirroring, you'll need to **whitelist the following domains**:

- `repo.anaconda.com`
- `anaconda.org`
- `conda.anaconda.org`
- `binstar-cio-packages-prod.s3.amazonaws.com`

If any Anaconda Enterprise users will use the local graphical program Anaconda Navigator in online mode, they will need access to these sites, which may need to be whitelisted in your network's firewall settings.

- <https://repo.anaconda.com> (or for older versions of Navigator and Conda, <https://repo.continuum.io>)
- <https://conda.anaconda.org> if any users will use conda-forge and other channels on Anaconda Cloud (`anaconda.org`)
- <https://vscode-update.azurewebsites.net/> if any users will install Visual Studio Code
- `google-public-dns-a.google.com` (8.8.8.8:53) to check internet connectivity with [Google Public DNS](#)

TLS/SSL certificate requirements

Anaconda Enterprise uses certificates to provide transport layer security for the cluster. To get you started, self-signed certificates are generated during the initial installation. You can configure the platform to use organizational TLS/SSL certificates after completing the installation.

You may purchase certificates commercially, or generate them using your organization's internal public key infrastructure (PKI) system. When using an internal PKI-signed setup, the CA certificate is inserted into the Kubernetes secret.

In either case, the configuration will include the following:

- a certificate for the root certificate authority (CA),
- an intermediate certificate chain,
- a server certificate, and
- a private server key.

See [Updating TLS/SSL certificates](#) for more information.

DNS requirements

Web browsers use domain names and web origins to separate sites, so they cannot tamper with each other. Anaconda includes deployments from many users, and if these deployments had addresses on the same domain, such as `https://anaconda.yourdomain.com/apps/001` and `https://anaconda.yourdomain.com/apps/002`, one app could access the cookies of the other, and JavaScript in one app could access the other app.

To prevent this potential security risk, Anaconda assigns deployments unique addresses such as `https://uuid001.anaconda.yourdomain.com` and `https://uuid002.anaconda.yourdomain.com`, where “yourdomain.com” is replaced with your organization's domain name, and `uuid001` and `uuid002` is replaced with dynamically generated universally unique identifiers (UUIDs), for example.

To facilitate this, Anaconda Enterprise requires the use of wildcard DNS entries that apply to a set of domain names such as `*.anaconda.yourdomain.com`.

For example, if you are using the fully qualified domain name (FQDN) `anaconda.yourdomain.com` with a master node IP address of `12.34.56.78`, the DNS entries would be as follows:

```
anaconda.yourdomain.com IN A 12.34.56.78
*.anaconda.yourdomain.com IN A 12.34.56.78
```

The wildcard subdomain's DNS entry points to the Anaconda Enterprise master node.

The master node's hostname and the wildcard domains must be resolvable with DNS from the master nodes, the worker nodes, and the end user machines. To ensure the master node can resolve its own hostname, any `/etc/hosts` entries used must be propagated to the gravity environment.

Existing installations of `dnsmasq` will conflict with Anaconda Enterprise. If `dnsmasq` is installed on the master node or any worker nodes, you'll need to remove it from all nodes *before installing Anaconda Enterprise*.

Run the following commands to ensure `dnsmasq` is stopped and disabled:

- To stop `dnsmasq`: `sudo systemctl stop dnsmasq`

- To disable dnsmasq: `sudo systemctl disable dnsmasq`
- To verify dnsmasq is disabled: `sudo systemctl status dnsmasq`

Browser requirements

Anaconda Enterprise supports the following web browsers:

- Chrome 39+
- Firefox 49+
- Safari 10+

The minimum browser screen size for using the platform is 800 pixels wide and 600 pixels high.

Note: JupyterLab and Jupyter Notebook don't currently support Internet Explorer, so Anaconda Enterprise users will have to use another editor for their Notebook sessions if they choose to use that browser to access the AE platform.

1.2 Cloud performance requirements

The *installation requirements for Anaconda Enterprise* are the same whether you choose to install the platform on premises, hosted VSphere, or on a cloud server. The only cloud-specific requirement for running Anaconda Enterprise relates to performance, so ensure your chosen cloud platform meets these minimum specifications before you begin:

Amazon Web Services (AWS)

Due to etcd's sensitivity to disk latency, only use EC2 instances with a minimum of 3000 IOPS. We recommend an instance type no smaller than `m4.4xlarge` for both master and worker nodes.

Microsoft Azure

To meet CPU and disk I/O requirements, the minimum size for the selected VM should be Standard D16s v3 (16 VCPUs, 64 GB memory).

Google Cloud Platform (GCP)

No requirements for installing Anaconda Enterprise are unique to Google Cloud Platform.

After you've verified that your system meets these performance requirements—as well as all system requirements—you are ready to *installing the cluster*.

1.3 Pre-install checklist

It's essential that the systems in your environment where you will install Anaconda Enterprise meet *ALL of the requirements outlined here*. The installer performs some pre-flight checks, and only allows installation to continue on nodes that are configured correctly, but doesn't verify *all requirements* are met.

We've created this pre-install checklist to help you **verify that you've accounted for everything before you begin**, and ensure your installation is successful. Consider printing out a copy and physically checking off items as you go.

Note: We've also packaged a pre-flight script that you can use to verify whether the systems on which you plan to install Anaconda Enterprise meet the minimum requirements to install successfully. Follow these instructions to install and run the script.

[] I've verified that all nodes in the cluster meet *the minimum or recommended specifications* for CPU, RAM and disk space.

[] I've verified that all nodes in the cluster meet *the minimum IOPS required* for reliable performance.

[] I've verified that there is *50GB of free space available* in the `/tmp` directory (or another temporary directory to be used during installation) on each node in the cluster.

[] I've verified that **all cluster nodes are operating the same version of the OS**, and that *the OS version is supported* by Anaconda Enterprise.

[] I've used the Network Time Protocol (NTP) to synchronize computer system clocks, and I've verified that **the clock of each node in the cluster is in sync with the others**. (Instructions for using NTP are provided [here](#).)

[] I've verified that I have `sudo` access on all systems, and *the firewall is configured correctly*.

[] I've verified that *all required kernel modules* are loaded.

[] I've verified that *the system control settings* are set correctly.

[] I've verified that any GPUs to be used with Anaconda Enterprise have *a supported NVIDIA CUDA driver installed*.

[] I've verified that the system meets *all network port requirements*, whether the specified ports need to be open internally, externally, or during installation only.

[] I've verified that any firewalls used for network security have been *temporarily* disabled, for the window of time when Anaconda Enterprise is being installed.

[] I've verified that the domains required for *online* package mirroring have been whitelisted, if applicable.

[] *If I intend to replace the self-signed certificates generated during installation with others*, I've gathered *all the information and files for the TLS/SSL certificates I will use*.

[] I've verified that the Anaconda Enterprise domain get resolved to the IP address of the master node, whether through an alias (A) record or canonical name (CNAME).

[] I've verified that any wildcard DNS entries for my organization's domain names meet *the DNS requirements outlined here*.

[] I've verified that the `/etc/resolve.conf` file on all the nodes **DOES NOT** include the `rotate` option.

[] I've verified that any existing installations of Docker (and `dockerd`), `dnsmasq`, and `lxd` have been removed from all nodes, as they will conflict with Anaconda Enterprise.

[] I've verified that all web browsers to be used to access Anaconda Enterprise are *supported by the platform*.

1.4 Installing the cluster

After you have determined the initial topology for your Anaconda Enterprise cluster, and verified that your system meets all of the *installation requirements*, you're ready to install the cluster.

Before you begin:

Note: If you haven't already, consider using the *pre-install checklist* provided, to verify that you've accounted for everything before you begin.

- By default, Anaconda Enterprise installs using a service account with the user ID (UID) 1000. You can change the UID of the service account by using the `--service-uid` option or the `GRAVITY_SERVICE_USER` environment variable *at installation time*. To do so, you need to have first created a group for that user with the UID.

For example, to use UID 1001, run the following commands **on each node of the cluster**:

```
root$ groupadd mygroup -g 1001
root$ useradd --no-create-home -u 1001 -g mygroup myuser
```

- The installer uses the `TMPDIR` directory that's configured on the master node, so **be sure the default directory contains sufficient space** or create an alternate directory (with sufficient space) for the installer to use. If you choose to use an alternate directory, ensure it has the correct permissions enabled (`drwxrwxrwx`), and either add it to `/etc/environment` or explicitly specify the directory during installation.

Determine your install method

The method you use to install the cluster will vary, depending on your ability to access the target machine. If you have network access to the target machine, we recommend you install Anaconda Enterprise *using a web browser*. Otherwise, you'll need to *use a command line*.

With both methods, you can create any number of nodes from one to five nodes. You can also add or remove nodes at any time after installation. For more information, see *Adding and removing nodes*.

If the cluster where you will install AE cannot connect to the internet, follow the instructions for *Installing in an air-gapped environment*.

Using a web browser (recommended)

1. On the master node, download and decompress the installer, replacing `<location_of_installer>` with the location of the installer, and `<version>` with your installer version:

```
curl -O <location_of_installer>.tar.gz
tar xvf anaconda-enterprise-<version>.tar.gz
cd anaconda-enterprise-<version>
```

2. On the master node, run the *pre-installation system checks* as `sudo` or `root` user before proceeding with the installation:

```
sudo ./gravity check --profile ae-master
```

3. To perform system checks *on a worker node*, run the following command as `sudo` or `root` user:

```
sudo ./gravity check --profile ae-worker
```

If all of the system checks pass and all requirements are met, the output from the above commands will be empty. If the system checks fail and some requirements are not met, the output will indicate which system checks failed.

4. After doing the pre-installation system checks, run the installer on the master node *as sudo or root user*:

```
sudo ./gravity wizard
```

Note: If you're using a service account UID that's different than the default 1000, append the command with the actual UID. For example, to use UID 1001, run `sudo ./gravity wizard --service-uid=1001`.

If you're using an alternate `TMPDIR`, pre-pend the command with the directory. For example, `sudo TMPDIR=/mytmp ./gravity wizard`

```
Tue Oct 29 14:22:22 UTC      Starting enterprise installer

To abort the installation and clean up the system,
press Ctrl+C two times in a row.

If the you get disconnected from the terminal, you can reconnect to the installer
agent by issuing 'gravity resume' command.

If the installation fails, use 'gravity plan' to inspect the state and
'gravity resume' to continue the operation.
See https://gravitational.com/gravity/docs/cluster/#managing-an-ongoing-operation for
↪details.


Tue Oct 29 14:22:22 UTC      Connecting to installer
Tue Oct 29 14:22:27 UTC      Connected to installer
Tue Oct 29 14:22:28 UTC      Starting web UI install wizard
Tue Oct 29 14:22:28 UTC      Open this URL in browser: https://172.31.67.113:61009/
↪web/installer/new/gravitational.io/AnacondaEnterprise/5.4.0-36.gdf45da616?install_
↪token=9954bf9f357b0eff8d2d2a4a48c8d9e6
Tue Oct 29 14:22:28 UTC      Waiting for the operation to start
```

5. To start the browser-based install, copy the full URL that is generated into your browser. *Ensure that you are connecting to the public network interface.*


NOTES:

- If you're using an alternate `TMPDIR` and DID NOT add it to `/etc/environment`, edit the copied URL to include the directory in the `sudo bash` command. For example, `sudo TMPDIR=/mytmp bash`.

- If you're unable to connect to the URL due to security measures in place at your organization, select **File > New Incognito Window** to launch the installer.
6. The installer will install a self-signed TLS/SSL certificate, so you can click the link at the bottom of this warning message to proceed:



7. After reviewing the License Agreement, check **I Agree To The Terms** and click **Accept**.
8. Enter the name to use for your deployment in the **Cluster Name** field. The **Bare Metal** option is already selected, so you can click **Continue**.



9. Select the number of nodes—between one and five—that you want to install in the cluster. One node will act as the master node, and any remaining nodes will be worker nodes. See *Fault tolerance* for more information on how to size your cluster.
10. *On each node* you plan to install Anaconda Enterprise, copy and run the command that's provided as it applies to the master node and any worker nodes. As you run the command on each node, the host name of the node is listed below the nodes.

1. Cluster name 2. **Capacity** 3. Installation 4. Create Admin

How many nodes do you want?

1 node 3 node 5 node

1 NODE Anaconda Enterprise master node
REQUIREMENTS - RAM: 4GB, CPU: Core x 4

COPY AND PASTE THE COMMAND BELOW INTO TERMINAL. YOUR SERVER WILL AUTOMATICALLY APPEAR IN THE LIST

```
curl -s --insecure -H "Host: 172.31.67.113:8080" https://172.31.67.113:8080/1954b19f3578b4f18d2d2a4a81b5d9e/ana-master" | sudo bash
```

2 NODES Anaconda Enterprise worker node(s)
REQUIREMENTS - RAM: 4GB, CPU: Core x 4

COPY AND PASTE THE COMMAND BELOW INTO TERMINAL. YOUR SERVER WILL AUTOMATICALLY APPEAR IN THE LIST

```
curl -s --insecure -H "Host: 172.31.67.113:8080" https://172.31.67.113:8080/1954b19f3578b4f18d2d2a4a81b5d9e/ana-worker" | sudo bash
```

About this step

Drag the slider to estimate the number of resources needed for that performance level. You can also add / remove resources after the installation.

Once you click "Start Installation" the resources will be provisioned on your infrastructure.

How many nodes do you want?

1 node 2 node 5 node

1 NODE Anaconda Enterprise master node
REQUIREMENTS - RAM: 4GB, CPU: Core x 4

COPY AND PASTE THE COMMAND BELOW INTO TERMINAL. YOUR SERVER WILL AUTOMATICALLY APPEAR IN THE LIST

```
curl -s --insecure -H "Host: 172.31.67.113:8080" https://172.31.67.113:8080/1954b19f3578b4f18d2d2a4a81b5d9e/ana-master" | sudo bash
```

HOSTNAME	IP ADDRESS	APP-SKIN
ip-172-31-67-113.ec2.internal	172.31.67.113	/opt/anaconda

CONTINUE **VERIFY**

About this step

Drag the slider to estimate the number of resources needed for that performance level. You can also add / remove resources after the installation.

Once you click "Start Installation" the resources will be provisioned on your infrastructure.

11. Use the **IP Address** drop-down to select the IP address for each node.
12. Accept the default directory for installing application data (`/opt/anaconda/`) or enter another location.
13. After all nodes are listed, click **Continue**. This process can take approximately 20 minutes to complete.

1. Cluster name 2. Capacity 3. **Installation** 4. Create Admin

Installation

Progress bar: 100%

Gathering Instances	Configure and install	Finalizing install
Provisioning instances	Preparing configuration	Installing application
Connecting to instances	Installing dependencies	Verifying application
Verifying instances	Installing platform	Connecting to application


EXECUTABLE LOGS

About this step


Your infrastructure is being provisioned and your application is being installed.

Once the installation is complete you will be taken to your infrastructure where you can access your application.

Note: To view the install logs, click the **EXECUTABLE LOGS** pulldown at the bottom of the panel.



When the installation is complete, the following screen is displayed:



14. Click **Continue & Finish Setup** to proceed to *Post-install configuration*.

Note: The installer running in the terminal will note that installation is complete and that you can stop the installer process. **Do not do so** until you have completed the *post-install configuration*.

Using a command line

If you cannot connect to the server from a browser—because you’re installing from a different network, for example—you can install Anaconda Enterprise using a command line.

On each node in the cluster, download and decompress the installer, replacing `<location_of_installer>` with the location of the installer, and `<version>` with your installer version:

```
curl -O <location_of_installer>.tar.gz
tar xvf anaconda-enterprise-<version>.tar.gz
cd anaconda-enterprise-<version>
```

On the *master node*, run the pre-installation system checks—as sudo or root user—before proceeding with the installation:

```
sudo ./gravity check --profile ae-master
```

Create a file named `values.yaml` with the following values, replacing `HOSTNAME` with the fully-qualified domain name (FQDN) of the host server:

```
apiVersion: v1
kind: ConfigMap
metadata:
  name: anaconda-enterprise-install
data:
  values: |
    hostname: HOSTNAME
    generateCerts: true
    keycloak:
      includeMasterRealm: true
```

After running the pre-installation system checks and creating the YAML file, run the following command *on the master node* as sudo or root user, where you replace:

- The `advertise-addr` IP address with the address you want to be visible to the other nodes
- `CLUSTERNAME` with a name, otherwise a random cluster name will be assigned
- `/path/to/values.yaml` with the path to the `values.yaml` file you created

For `flavor`, choose from the following options the one that represents the number and type of nodes you want to install in the cluster:

- `small`: installs a single-node cluster (one ae-master node). This is the default flavor.
- `medium`: installs three nodes (one ae-master node and two ae-worker nodes)
- `large`: installs five nodes (one ae-master node, two k8s-master nodes and two ae-worker nodes):

```
sudo ./gravity install --advertise-addr=192.168.1.1 --token=anaconda-enterprise --
↪cluster=CLUSTERNAME --flavor=small --config /path/to/values.yaml
```

NOTES:

If you're using a service account UID that's different than the default 1000, append the command with the actual UID. For example, to use UID 1001, run:

```
sudo ./gravity install --advertise-addr=192.168.1.1 --token=anaconda-enterprise --
↪cluster=CLUSTERNAME --flavor=small --config /path/to/values.yaml --service-uid=1001

-or-

sudo GRAVITY_SERVICE_USER=1001 ./gravity install --advertise-addr=192.168.1.1 --
↪token=anaconda-enterprise --cluster=CLUSTERNAME --flavor=small --config /path/to/
↪values.yaml
```

If you're using an alternate `TMPDIR`, pre-pend the command with the directory. For example:

```
sudo TMPDIR=/mytmp ./gravity install --advertise-addr=192.168.1.1 --token=anaconda-
↪enterprise --cluster=CLUSTERNAME --flavor=small --config=/path/to/values.yaml
```

The command line displays the installer's progress:

```
* [0/100] starting installer
* [0/100] preparing for installation... please wait
* [0/100] application: AnacondaEnterprise:5.2.x
* [0/100] starting non-interactive install
* [0/100] still waiting for 1 nodes of role "worker" to join
* [0/100] still waiting for 1 nodes of role "worker" to join
* [0/100] still waiting for 1 nodes of role "worker" to join
* [0/100] initializing the operation
* [20/100] configuring packages
* [50/100] installing software
```

If you're installing AE on AWS, use the `--cloud-provider` option when installing the master. The installer automatically detects EC2 and uses the VPC-based flannel backend instead of VXLAN. **To force the use of VXLAN**, use the `--cloud-provider generic` option.

On each worker node, run the following command, replacing the `advertise-addr` IP address with the address you want to be visible to the other nodes:

```
sudo ./gravity join 192.168.1.1 --advertise-addr=192.168.1.2 --token=anaconda-
↪enterprise --role=ae-worker
```

The command line displays the installer's progress:

```
* [0/100] joining cluster
* [0/100] connecting to cluster
* [0/100] connected to installer at 192.168.1.1
* [0/100] initializing the operation
* [20/100] configuring packages
* [50/100] installing software
```

This process takes approximately 20 minutes.

After you've finished installing Anaconda Enterprise, you'll need to create a local user account and password to log into the Anaconda Enterprise Operations Center.

First, enter the Anaconda Enterprise environment *on any of the master or worker nodes*:

```
sudo gravity enter
```

Then, run the following command to create a local user account and password for the Anaconda Enterprise Operations Center, replacing `<your-email>` and `<your-password>` with the email address and password you want to use.

Note: Passwords must be at least six characters long.

```
gravity --insecure user create --type=admin --email=<your-email> --password=<your-
↪password> --ops-url=https://gravity-site.kube-system.svc.cluster.local:3009
```

Installing in an air-gapped environment

If the cluster where you will install Anaconda Enterprise *cannot connect to the internet*, follow these instructions:

1. Download the installer tarball file to a jumpbox or USB key.

2. Move the installer tarball file to a designated head node in the cluster.
3. Untar the installer file and run `sudo ./gravity wizard` for browser-based installation or `sudo ./gravity install` for CLI-based installation.

Installation and post-install configuration steps are the same for air-gapped and internet-connected installations, so you can continue the installation process from this point, choosing your preferred method:

- *Browser installation* (must be on the same network as the target machines)
- *Unattended command-line interface (CLI) installation*

Post-install configuration

After completing either installation path, complete the *post-install configuration steps*.

1.5 Post-install configuration

There are a few platform settings that need to be updated *after installing Anaconda Enterprise*, before you can begin using it. Follow the instructions below, based on whether you used *a web browser* or *a command-line* to *install the platform*. Then you'll be ready to test your installation and perform additional configuration, specific to your organization.

1.5.1 Browser-based instructions

If you installed Anaconda Enterprise using a web browser, a UI will guide you through some post-install configuration steps.

Note: It may take a moment for the **Post-Install Setup** screen to appear. If you see an error immediately after clicking **Continue** at the end of the installation process, please refresh your browser after a few seconds to display the UI.

AnacondaEnterprise v5.4.0-36.gdf45da616 Post-Install Setup

Congratulations! You have successfully installed AnacondaEnterprise. This is the last step to finish your setup.

Email
This user will serve as the cluster administrator.

Password
Must be at least 6 characters.

Confirm Password

SSL Certificates
In order to keep your Anaconda Enterprise installation secure, we recommend using your own SSL certificates -- please configure these in the admin UI after installation.

☐ Generate temporary certificates

1. Enter the cluster Admin account credentials that you will use to log in to the Anaconda Enterprise Operations Center initially, and click **Next**. (You can change these, or [authorize additional Operations Center Admins](#), as needed.)

Note: The installer will generate self-signed SSL certificates that you can use temporarily to get started. See `../admin/advanced/certs` for information on how to change them later, if desired.

2. Enter the fully-qualified domain name (FQDN) where the cluster will be accessed and click **Finish Setup**.
3. Log in to the Anaconda Enterprise Operations Center using the cluster Admin credentials you provided in Step 1, and follow the instructions below to update the platform settings with the FQDN of the host server.

1.5.2 Command-line instructions

If you performed an unattended installation using [the command-line instructions](#), follow the instructions below to generate self-signed SSL certificates that you can use temporarily to get started. See `../admin/advanced/certs` for information on how to change them later, if desired.

Note: You need to have OpenJDK installed to be able to use the following method to generate self-signed SSL certificates.

1. *On the master node* for your Anaconda Enterprise installation, run the following commands to save your secrets file to a location where Anaconda Enterprise can access it, replacing `YOUR_FQDN` with the fully-qualified domain name of the cluster on which you installed Anaconda Enterprise.:

```
cd path/to/Anaconda/Enterprise/unpacked/installer
cd DIY-SSL-CA
bash create_noprompt.sh YOUR_FQDN
cp out/DESIRED_FQDN/secret.yml /var/lib/gravity/planet/share/secret.yml
```

Now `/var/lib/gravity/planet/share/secret.yml` is accessible as `/ext/share/secret.yml` within the Anaconda Enterprise environment, which can be accessed with the following command:

```
sudo gravity enter
```

2. Replace the default secrets cert with the contents of your `secret.yml` file by running the following commands from within the Anaconda Enterprise environment:

```
$ kubectl delete secrets anaconda-enterprise-certs
secret "anaconda-enterprise-certs" deleted
$ kubectl create -f /ext/share/secret.yml
secret "anaconda-enterprise-certs" created
```

Note: If the post-install process doesn't complete after using the CLI install, you can complete the process by running the following command *within gravity*.

To complete the post-install process:

```
gravity --insecure site complete
```

Now you are ready to follow the instructions below to [test your installation](#).

1.5.3 Testing your installation

After you’ve finished *installing Anaconda Enterprise*, and completed the post-install configuration steps, you can do the following to verify that your installation succeeded:

1. Access the Anaconda Enterprise console by entering the URL of your AE server in a web browser: `https://anaconda.example.com`, replacing `anaconda.example.com` with the fully-qualified domain name of the host server.
2. Login with the default username and password `anaconda-enterprise/anaconda-enterprise`. After testing your installation, update the credentials for this default login. See *Configuring user access* for more information.

You can verify a successful installation by doing any or all of the following:

- *Creating* a new project and starting an editing session
- *Deploying* a project
- *Generating a token* from a deployment

Note: Some of the sample projects can only be deployed after *mirroring the package repository*. To test your installation without doing this first, you can deploy the “Hello Anaconda Enterprise” sample project.

Next steps:

Now that you’ve completed these *essential* steps, you can do any of the following optional steps:

- *Install the Anaconda Enterprise CLI.*
- *Install conda for package mirroring.*
- *Install Livy server for Hadoop Spark access.*
- Set TLS/SSL certificates for the platform.

1.6 Updating TLS/SSL certificates

You can replace the self-signed certificates generated as part of the *initial post-install configuration* at any time.


Before you begin, follow the processes outlined below. Then you can update the Anaconda Enterprise platform to use your own certificates using *the Anaconda Enterprise Admin Console* or *the command line*.


Before you begin:

1. Ask all users to save their work, stop any sessions and deployments, and log out of the platform while you update the certificates.
2. Backup your current Anaconda Enterprise configuration following the *backup process*.
3. Gather all of the following information and files related to your certificates, so you have it available to copy and paste from in the procedure that follows:
 - Registered domain name for the server
 - SSL certificate for `servername.domain.tld`, named `tls.crt`
 - SSL private key for `servername.domain.tld`, named `tls.key`
 - Root SSL certificate (such as [this default Root CA](#)), named `rootca.crt`. *A root certificate is optional but recommended.*

- Intermediate SSL certificate chain/bundle, named `intermediate.pem` (This certificate may also appear as the second entry in your `fullchain.pem` file.)
 - Wildcard domain name
 - Wildcard certificate for `*.servername.domain.tld`, named `wildcard.crt`.
 - Wildcard private key for `*.servername.domain.tld`, named `wildcard.key`.
4. After you've gathered all the information above, follow the steps below that correspond to whether you will use the Admin console or *the command line* to update the Anaconda Enterprise platform to use your certificates.

To update the platform using the Admin console:

1. Log in to Anaconda Enterprise, select the **Menu** icon  in the top right corner and click the **Administrative Console** link displayed at the bottom of the slide out window.
2. Log in to the console using the Administrator credentials *configured after installation*.
3. Select **Web Certificates** from the left menu.



4. Copy and paste the certificate and key information from the files you gathered previously into the appropriate fields.
5. Click **Save** to update the platform with your changes.

Note: The default SSL certificate file names generated by the installer vary slightly between versions. *If you have upgraded from a previous version of Anaconda Enterprise*, you may need to update your configuration to make sure all services are referencing the correct SSL certificate filenames (see below).

Previous	Updated
rootca.pem	rootca.crt
cert.pem	tls.crt
privkey.pem	tls.key
tls.crt	wildcard.crt
tls.key	wildcard.key

Note: The `keystore.jks` filename remains unchanged.

To update the platform using the command line:

On the system where the certificate and private key reside:

1. Install `openjdk`. For example, use the following command to install `java-1.8.0-openjdk` on CentOS 7.5:

```
yum install java-1.8.0-openjdk -y
```

2. Run the following command to create the `keystore.jks` file that will be used by Java:

```
openssl pkcs12 -passout pass:anaconda -export -in CERT.PEM -inkey KEY.PEM -out ↵
↵certificate.pl2 -name auth
keytool -importkeystore -deststorepass anaconda -destkeypass anaconda -
↵destkeystore keystore.jks -srckeystore certificate.pl2 -srcstoretype PKCS12 -
↵srcstorepass anaconda -alias auth
```

Note: If you're using a certificate provided by Let's Encrypt, use `FULLCHAIN.PEM` instead of `CERT.PEM`.

3. Create an updated Root CA to use with the system:

```
cat ROOT.CA /etc/ssl/certs/ca-bundle.trust.crt > updated-trust-ca.crt
```

Note: If you're using a certificate provided by Let's Encrypt you can obtain the Root CA [here](#). You must also prepend the `CHAIN.PEM` to the Root CA.

Note: For RHEL-based systems, the path to the trusted CA is: `/etc/ssl/certs/ca-bundle.trust.crt`. For Ubuntu-based systems, the path to the system CA is `/etc/ssl/certs/ca-certificates.crt`.

4. Setup the basic structure of the `certificates.yaml` file, that you'll be updating in the next several steps:

```
cat > certificates.yaml <<EOL
apiVersion: v1
kind: Secret
metadata:
```

(continues on next page)

(continued from previous page)

```
name: anaconda-enterprise-certs
type: Opaque
data:
EOL
```

5. Add the main domain for the SSL certificate. For example `test.anaconda.com`:

```
printf "  tls.crt: " >> certificates.yaml
base64 -i --wrap=0 CERT.PEM >> certificates.yaml
```

6. Add the private key for the certificate:

```
printf "\n  tls.key: " >> certificates.yaml
base64 -i --wrap=0 KEY.PEM >> certificates.yaml
```

7. Add the SAN certificate to the file. For example `*.test.anaconda.com`:

```
printf "\n  wildcard.crt: " >> certificates.yaml
base64 -i --wrap=0 CERT.PEM >> certificates.yaml
```

8. Add the private key for the SAN certificate:

```
printf "\n  wildcard.key: " >> certificates.yaml
base64 -i --wrap=0 KEY.PEM >> certificates.yaml
```

9. Add the keystore you generated in Step 2:

```
printf "\n  keystore.jks: " >> certificates.yaml
base64 -i --wrap=0 keystore.jks >> certificates.yaml
```

10. Add the updated Root CA that you created in Step 3:

```
printf "\n  rootca.crt: " >> certificates.yaml
base64 -i --wrap=0 updated-trust-ca.crt >> certificates.yaml
```

11. Add a new line at the end of the file:

```
printf '\n' >> certificates.yaml
```

12. Copy the file to the share directory inside gravity:

```
cp certificates.yaml /var/lib/gravity/planet/share
```

13. Run the following commands to enter gravity and list your secrets:

```
gravity enter
kubectl get secrets
```

14. In the next step you'll be removing and recreating a secret, so create a backup of the existing secrets first:

```
kubectl get secret anaconda-enterprise-certs -o yaml --export > anaconda_certs.
↪ backup
```

15. Remove the existing secret, and recreate it from the file you placed in the share directory (in Step 12):

```
kubectl delete secret anaconda-enterprise-certs
kubectl create -f /ext/share/certificates.yaml
```

16. Restart all pods to update Anaconda Enterprise to use your certificate:

```
kubectl get pods | cut -d' ' -f1 | xargs kubectl delete pods
```

1.6.1 Extracting TLS/SSL certificates

Run the following command for each certificate file you wish to extract, replacing `rootca.crt` below with the name of the specific file:

```
kubectl get secrets anaconda-enterprise-certs -o jsonpath="{.data['rootca\.crt']}" |   
↪base64 -d > rootca.crt
```

The following certificate files are available:

- `rootca.crt`: the root certificate authority bundle
- `tls.crt`: the SSL certificate for individual services
- `tls.key`: the private key for the above certificate
- `wildcard.crt`: the SSL certificate for “wildcard” services, such as deployed apps and sessions
- `wildcard.key`: the private key for the above certificate
- `keystore.jks`: the Java Key Store containing these certificates used by some services

To copy the extracted root certificate and add it to the default RHEL/CentOS or Ubuntu trusted CA bundles, run the following commands:

```
# On Ubuntu
$ cp rootca.crt /usr/share/ca-certificates
$ update-ca-certificates

# RHEL/CentOS
$ cp rootca.crt /etc/pki/ca-trust/source/anchors/
$ update-ca-trust
```

1.6.2 Verifying TLS/SSL certificates

If you are using privately signed certificates, *extract the rootca*, then use `openssl` to verify the certificates and make sure the final `Verify return code` is 0:

```
# On Ubuntu
$ openssl s_client -connect anaconda.example.com:443 -CAfile /etc/ssl/certs/ca-  
↪certificates.crt
...
    Verify return code: 0 (ok)

# On RHEL/CentOS
```

(continues on next page)

(continued from previous page)

```
$ openssl s_client -connect anaconda.example.com:443 -CAfile /etc/pki/tls/certs/ca-  
↪bundle.crt  
...  
Verify return code: 0 (ok)
```

Note: The root CA for the *self-signed certificates generated as part of the installation* is contained in the certificate bundle at `/etc/pki/tls/certs/ca-bundle.crt`.

You can now *install and use the Anaconda Enterprise CLI* to configure the certificates for the platform repository.

1.7 Installing conda for packaging mirroring

To help improve performance and security, Anaconda Enterprise enables you to create a local copy of an online package repository so users can access the packages from a centralized, on-premises location. This copy is called a *mirror*. A mirror can be complete, partial, or include specific packages or types of packages.

The Anaconda Enterprise installer contains a bootstrap executable that you can run to install conda.

Prerequisites:

- [Install Anaconda Enterprise](#)
- Complete the [post-install configuration](#)
- [Update TLS/SSL certs](#)

To install conda:

1. In a terminal window, navigate to the directory where you downloaded and extracted the Anaconda Enterprise installer, replacing `<version>` with your specific version number:

```
$ cd anaconda-enterprise-<version>\installer
```

2. Run the following command to verify whether the `bzip2` package is installed:

```
which bunzip2
```

If the command returns a valid package, you can run the bootstrap executable. Otherwise use your package manager to install the binary, using either `yum install bzip2` or `apt-get install bzip2`.

3. Run the following command to run the bootstrap executable:

```
$ ./conda-bootstrap-<version>
```

4. Type `yes` when prompted to accept the end user license agreement (EULA).
5. Accept the default path, or enter an alternate path when prompted.
6. When prompted, type `yes` to activate the conda command at shell initialization.
7. Re-initialize your terminal for the previous steps to take effect:

```
source ~/.bashrc
```

Now that you've installed conda, you can [configure access](#) to the source of the packages to be mirrored, whether an online repository or a tarball (if an air-gapped installation). Then you'll be ready to begin *mirroring channels and packages*.

1.8 Installing the Anaconda Enterprise CLI

Warning: The following process for installing the Anaconda Enterprise CLI results in a broken conda env. Follow [the workaround described here](#) instead, until the issue is addressed in a future release of Anaconda Enterprise.

If you want to be able to *create and share channels and packages* from your Anaconda repository using conda commands, you need to download and install the Anaconda Enterprise CLI. If you *updated the platform's TLS/SSL certificate*, you can also use the AE CLI to *configure the TLS/SSL certs for the repository*.

Prerequisites:

- [Install Anaconda Enterprise](#)
- Complete the [post-install configuration](#)
- [Install conda](#)

1. To install the CLI, run the following command, replacing `anaconda.example.com` with the fully-qualified domain name (FQDN) of your Anaconda Enterprise instance:

```
conda install -kc https://anaconda.example.com/repository/conda/anaconda-  
enterprise anaconda-enterprise-cli cas-mirror git
```

Note: You'll notice that running this command also installs `cas-mirror`, the package mirroring tool. For more information on package mirroring, see [Configuring channels and packages](#).

2. After the list of package dependencies has been resolved, type `y` to proceed with the installation.

1.8.1 Configuring the Anaconda Enterprise CLI

1. To add the url of the Anaconda repository to the set of available sites, run the following command with the fully-qualified domain name (FQDN) of your Anaconda Enterprise instance:

```
anaconda-enterprise-cli config set sites.master.url https://<your.domain.com>/  
repository/api
```

2. Run the following command to configure the instance of Anaconda repository you will be using as the default site:

```
anaconda-enterprise-cli config set default_site master
```

3. To see a consolidated view of the configuration, run the following command:

```
anaconda-enterprise-cli config view
```

The Anaconda Enterprise CLI reads configuration information from the following places:

System-level configuration: `/etc/anaconda-platform/cli.yml`

User-level configuration: `$INSTALL_PREFIX/anaconda-platform/cli.yml` and `$HOME/.anaconda/anaconda-platform/cli.yml`

To change how it's configured, modify the appropriate `cli.yml` file(s), based on your needs.

Note: Changing configuration settings at the user level overrides any system-level configuration.

If you *updated the platform's TLS/SSL certificate*, you can use the AE CLI to configure the certificates for the repository using the following commands:

```
$ anaconda-enterprise-cli config set ssl_verify true

# On Ubuntu
$ anaconda-enterprise-cli config set sites.master.ssl_verify /etc/ssl/certs/ca-
↪certificates.crt

# On RHEL/CentOS
$ anaconda-enterprise-cli config set sites.master.ssl_verify /etc/pki/tls/certs/ca-
↪bundle.crt
```

1.8.2 Logging in to the Anaconda Enterprise CLI

1. Run this command to access the CLI:

```
anaconda-enterprise-cli login
```

2. Log in to the CLI using the same username and password that you use to log in the Anaconda Enterprise web interface:

```
Username: <your-username>
Password: <your-password>
```

Next Steps: You can now *configure access* to the source of the packages to be mirrored, whether an online repository or a tarball (if an air-gapped installation). Then you'll be ready to begin *mirroring channels and packages*.

1.9 Installing Livy server for Hadoop Spark access

To support your organization's data analysis operations, Anaconda Enterprise enables platform users to connect to remote Apache Hadoop or Spark clusters. Anaconda Enterprise uses Apache Livy to handle session management and communication to Apache Spark clusters, including different versions of Spark, independent clusters, and even different types of Hadoop distributions.

Livy provides all the authentication layers that Hadoop administrators are used to, including Kerberos. AE also authenticates to HDFS with Kerberos. **Kerberos Impersonation must be enabled.**

When Livy is installed, users can connect to a remote Spark cluster when creating projects by selecting the Spark template. They can either use the Python libraries available on the platform, or package a specific environment to target for the job. For more information, see [Hadoop / Spark](#).

Before you begin:

Verify the connection requirements. The following table outlines the supported configurations for connecting to remote Hadoop and Spark clusters with Anaconda Enterprise.

Software	Version
Hadoop and HDFS	2.6.0+
Spark and Spark API	1.6+ and 2.X
Sparkmagic	0.12.7
Livy	0.5
Hive	1.1.0+
Impala	2.11+

Note: The Hive metastore may be Postgres or MySQL. The Livy server must run on an “edge node” or client in the Hadoop/Spark cluster. Verify that the `spark-submit` and/or the `spark repl` commands work on this machine.

Installing Livy

Follow the instructions below to install Livy into an existing Spark cluster, or download and install the official version of Livy.

Note: This example is specific to a Red Hat-based Linux distribution, with a Hadoop installation based on Cloudera CDH. To use other systems, you’ll need to look up the corresponding commands and locations.

1. Locate the directory that contains Anaconda Livy. Typically this will be `anaconda-enterprise-X.X.X-X.X.X/installer/anaconda-livy-0.5.0`, where `X.X.X-X.X` corresponds to the Anaconda Enterprise version.
2. Copy the entire directory that contains Anaconda Livy to an edge node on the Spark/Hadoop cluster.

After installing Livy server, you’ll need to configure it to work with Anaconda Enterprise. For example, you’ll need to enable impersonation, so users running Spark sessions are able to log in to each machine in the Spark cluster. For more information, see [Configuring Livy server for Hadoop Spark access](#).

1.10 Upgrading Anaconda Enterprise

The process of moving from one version of Anaconda Enterprise to another varies slightly, depending on which version you are migrating to and from, so follow the instructions that correspond to your Anaconda Enterprise implementation. If you’re moving from an implementation of AE 4 to AE 5, we consider that a *migration*. If you’re moving between point releases of the same version, we consider that an *upgrade*.

Migrating between major releases of Anaconda Enterprise requires Administrators to [migrate the package repository](#) and project owners to [migrate their notebooks](#).

Upgrading Anaconda Enterprise generally involves exporting or [backing up](#) your current package repository and all project data, [uninstalling](#) the existing version and [installing](#) the newer version, then importing or [restoring](#) this information on the new platform.



1.10.1 Upgrading between versions of AE5

Due to the potential complexity of your custom configuration, please contact Anaconda Support before initiating the upgrade.

After you have determined the topology for your Anaconda Enterprise cluster, and verified that your system meets all of the [installation requirements](#), you're ready to upgrade the cluster.

Before you begin:

- Configure your A record in DNS for the master node with the actual domain name you will use for your Anaconda Enterprise installation.
- If you are using a firewall for network security, we recommend you temporarily disable it while you upgrade Anaconda Enterprise.
- When installing Anaconda Enterprise on a system with multiple nodes, **verify that the clock of each node is in sync with the others prior to starting the installation process**, to avoid potential issues. We recommend using the Network Time Protocol (NTP) to synchronize computer system clocks automatically over a network. See instructions [here](#).
- Back up the `anaconda-enterprise-anaconda-platform.yml` file used to [configure the platform](#), as **config map settings such as external Git configuration are not automatically migrated to the new cluster as part of the upgrade process**.
- Back up your custom `cas-mirror` and `anaconda-enterprise-cli` configurations (see Step 4 below), as `$HOME/cas-mirror` will be overwritten during the upgrade process. To avoid any compatibility issues, we recommend you upgrade your mirror tools as part of the upgrade process. Afterwards, simply copy over the configuration files you backed up to restore your custom configuration.

Warning: After the upgrade or backup process has begun, it won't be possible to capture or back up data for any open sessions or deployments. We therefore recommend that you ask all users to save their work, stop any sessions and deployments, and log out of the platform during the upgrade window. The `backup.sh` script that runs as part of *the upgrade process* will *restart all pods*, so if they don't, they will lose any unsaved work. They may also encounter a 404 error after the upgrade. The workaround for the error message is to stop and restart the session or deployment that generated the error, but there is no way to retrieve lost data.

The upgrade process varies slightly, depending on your current version and which version you're installing. To update an existing Anaconda Enterprise installation to a newer version, follow the process that corresponds to your particular scenario:

- [Upgrading from AE 5.3.0/5.3.1 to 5.4.x](#)

- [Upgrading from AE 5.2.x/5.3.0 to 5.3.1](#)

Upgrading from AE 5.3.0/5.3.1 to 5.4.x

Anaconda Enterprise 5.3.0 and 5.3.1 supports in-place upgrades, so you can follow these simple steps to update your 5.3.0 or 5.3.1 installation to the latest version.

1. Ensure that all AE users have closed any open sessions, stopped any deployed applications, and logged out of the platform. The `backup.sh` script that runs as part of the upgrade process will restart all pods, so if they don't, they will lose any unsaved work.
2. On the master node running your current installation of AE, download and decompress the new installer, and then `cd` into the install directory, replacing `<location_of_installer>` with the location of the installer, and `<version>` with your installer version:

```
curl -O <location_of_installer>.tar.gz
tar xvzf anaconda-enterprise-<version>.tar.gz
```

3. Curl the shim download and untar the shim download. Then, `cd` into the shim:

```
curl -O <location_of_shim>.tar.gz
tar xvzf anaconda-enterprise-<version>-gravity-only.tar.gz
cd anaconda-enterprise-<version>-gravity-only
```

4. Run the following command to upload the installer to the AE environment:

```
sudo ./upload
```

5. When the upload process finishes, run the following command to start the upgrade process:

```
sudo ./gravity upgrade
```

6. Change directory to the install directory and rerun steps 4 and 5 above:

```
cd ../anaconda-enterprise-<version>
sudo ./upload
sudo ./gravity upgrade
```

7. Depending on your implementation, the upgrade process may take an hour or more to complete. You can check the status of the upgrade process by running `sudo ./gravity status`.

If you encounter errors while upgrading, you can check the status of the operation by running `sudo ./gravity plan`. You can then roll back any step in the upgrade process by running the `rollback` command against the name of the phase, as it's listed in the `Phase` column:

```
sudo ./gravity rollback --phase=/<name-of-phase>
```

After addressing the error(s), you can resume the upgrade by running the following command:

```
sudo ./gravity upgrade --resume --force
```

After the upgrade process completes, follow the steps to [verify that your upgrade was successful](#).

After you’ve confirmed that your upgrade was successful—and everything works as expected—you can *run a script* to remove images leftover from the previous installation and free up space. This will help prevent the cluster from running out of disk space on the master node.

Upgrading from AE 5.2.x/5.3.0 to 5.3.1

Anaconda Enterprise 5.2.x and 5.3.0 supports in-place upgrades, so you can follow these simple steps to update your 5.2.x or 5.3.0 installation to the latest version.

1. Ensure that all AE users have closed any open sessions, stopped any deployed applications, and logged out of the platform. The `backup.sh` script that runs as part of the upgrade process will restart all pods, so if they don’t, they will lose any unsaved work.
2. On the master node running your current installation of AE, download and decompress the new installer, replacing `<location_of_installer>` with the location of the installer, and `<version>` with your installer version:

```
curl -O <location_of_installer>.tar.gz
tar xvzf anaconda-enterprise-<version>.tar.gz
cd anaconda-enterprise<version>
```

3. Run the following command to upload the installer to the AE environment:

```
sudo ./upload
```

4. When the upload process finishes, run the following command to start the upgrade process:

```
sudo ./gravity upgrade
```

5. The upgrade process may take up to an hour to complete. You can check the status of the upgrade process by running `sudo ./gravity status`.

If you encounter errors while upgrading, you can check the status of the operation by running `sudo ./gravity plan`. You can then roll back any step in the upgrade process by running the `rollback` command against the name of the phase, as it’s listed in the `Phase` column:

```
sudo ./gravity rollback --phase=/<name-of-phase>
```

After addressing the error(s), you can resume the upgrade by running the following command:

```
sudo ./gravity upgrade --resume --force
```

After the upgrade process completes, follow the steps to *verify that your upgrade was successful*.

After you’ve confirmed that your upgrade was successful—and everything works as expected—you can *run a script* to remove images leftover from the previous installation and free up space. This will help prevent the cluster from running out of disk space on the master node.

Verify installation

After you’ve verified that all pods are running and updated the Anaconda Enterprise URLs, you can confirm that your upgrade was successful by doing the following:

1. Return to the Authentication Center and select **Users** in the **Manage** menu on the left.
2. Click **View all users** and verify that all user data has also been restored.
3. Access the Anaconda Enterprise user console by visiting this URL in your browser: `https://example.anaconda.com/`—replacing `example.anaconda.com` with the FQDN of your server—and logging in using the same credential you used in your previous installation.
4. Review the **Projects** list to verify that all project data has been restored.

Note: If you didn't configure SSL certificates as part of the post-install configuration, do so now. See [Updating TLS/SSL certificates](#) for more information.

If you're upgrading a cluster with external Git configured:

Note: The `git` section of the `anaconda-enterprise-anaconda-platform.yml` file used to configure Anaconda Enterprise 5.3.1 includes parameter changes. If you backed up your Anaconda Enterprise config map before upgrading, and copied it onto the newly-updated master node, you'll need to *update your config map with the new information as described here*.

If you're upgrading a Spark/Hadoop configuration:

After you successfully restore your Anaconda Enterprise data, run the following commands *on the master node* of the newly-installed Anaconda Enterprise server:

```
kubectl replace -f <path-to-anaconda-config-files-secrets.yaml>
```

To verify that your configuration upgraded correctly:

1. Log in to Anaconda Enterprise.
2. *If your configuration uses Kerberos authentication*, open a Hadoop terminal and authenticate yourself through Kerberos using the same credentials you used previously. For example, `kinit <username>`.
3. Open a Jupyter Notebook that uses Sparkmagic, and verify that it behaves as expected. For example, run the `sc` command to connect to Sparkmagic and start Spark.

After you've confirmed that your upgrade was successful, we recommend you run the following command to remove all unused packages and images from previous versions of the application, and repopulate the registry to include only those images required by the current version of the application:

```
sudo gravity gc
```

The command's progress is displayed in the terminal, so you can watch as it marks packages associated with the latest version as required, and deletes older versions.

If running the command generates an error, you can resume the command (after you fix the issue that caused the error) by running the following command:

```
sudo gravity gc ---resume
```

1.10.2 Backing up and restoring AE

Before you begin any upgrade, you must back up your Anaconda Enterprise configuration and data files. You may also choose to back up AE regularly, based on your organization's disaster recovery policies.

CAUTION: After the back up process has begun, it won't be possible to back up data for any open sessions or deployments. We therefore recommend that you ask all users to save their work, stop any sessions and deployments, and log out of the platform during the upgrade window. If they don't, they will lose any unsaved work. They may also encounter a 404 error after the upgrade. The workaround for the error message is to stop and restart the session or deployment that generated the error, but there is no way to retrieve lost data.

If you are performing backing up Anaconda Enterprise as part of an upgrade, note that *after installing AE 5.2.x*, you'll need to re-configure your SSL certificates, so ensure all certificate-related information—including the private key—is accessible at that point in the process. See [upgrading between versions for AE5](#) for the complete upgrade process.

Backing up Anaconda Enterprise

The number of channels and packages being backed up will impact the amount of free space and time required to perform the backup, so ensure you have sufficient free space and time available to complete the process. To prevent potential disk pressure issues, you can create another volume and specify that location instead of the default `/opt/anaconda`. See [Troubleshooting known issues](#) for more information.

All of the following commands should be run on the master node.

1. Copy the `backup.sh` script from the location where you saved the installer tarball to the Anaconda Enterprise environment using the following command:

```
sudo cp backup.sh /opt/anaconda
```

2. Back up Anaconda Enterprise by running the following commands:

```
cd /opt/anaconda
bash backup.sh
```

The following backup files are created and saved to `/opt/anaconda`:

```
ae5-data-backup- $\{timestamp\}$ .tar
ae5-state-backup- $\{timestamp\}$ .tar.gz
```

3. Move the backup files to a remote location to preserve them, as the `/opt/anaconda` directory will be deleted in future steps. *After uninstalling AE*, you'll copy `ae5-data-backup- $\{timestamp\}$.tar` back to your local filesystem.
4. Exit the Anaconda Enterprise environment by typing `exit`.

If your existing configuration includes Spark/Hadoop, perform these additional steps to migrate configuration information specific to your cluster:

1. Run the following command to retrieve configuration info. from the 5.1.x server, and generate the `anaconda-config-files-secret.yaml` file:

```
kubectl get secret anaconda-config-files -o yaml > <path-to-anaconda-config-files-
↪secret.yaml>
```

NOTE: This file will be deleted in future steps, so **move it to a remote location to preserve it**, and ensure that you can access this file from the server where you're installing the newer version of AE 5.2.x.

2. Open the `anaconda-config-files-secret.yaml` file, locate the metadata section, and delete everything under it except for the following: `name: anaconda-config-files`.

For example, if it looks like this to begin with:

```
apiVersion: v1
data:
  xxxx
kind: Secret
metadata:
  creationTimestamp: 2018-07-31T19:30:54Z
  name: anaconda-config-files
  namespace: default
  resourceVersion: "981426"
  selfLink: /api/v1/namespaces/default/secrets/anaconda-config-files
  uid: 3de10e2b-94f8-11e8-94b8-1223fab00076
type: Opaque
```

It will look like this afterwards:

```
apiVersion: v1
data:
  xxxx
kind: Secret
metadata:
  name: anaconda-config-files
type: Opaque
```

Restoring Anaconda Enterprise

If you backed up your Anaconda Enterprise installation, you can restore configuration information from the backup files. The restore script restores data, and can be optionally used to restore state information.

NOTE: When upgrading from 5.1.x to 5.2.x, we recommend restoring only *data* from the backup, and using the *state* generated during installation of 5.2.0. See [upgrading between versions for AE5](#) for the complete upgrade process.

Copy the `restore.sh` script from the location where you saved the installer tarball to the Anaconda Enterprise environment using the following command:

```
sudo cp restore.sh /opt/anaconda
```

To restore only data, run:

```
cd /opt/anaconda/
bash restore.sh <path-to-data-backup-file>
```

NOTE: Replace `path-to-data-backup-file` with the path to the data backup file generated when you ran the Anaconda Enterprise backup script.

To restore data and state, run:

```
cd /opt/anaconda/  
bash restore.sh <path-to-data-backup-file> <path-to-state-backup-file>
```

For help, run the `bash restore.sh -h` command.

After recovery, manually stop and restart all active sessions and deployments and job runs with the UI.

1.10.3 Uninstalling AE

Before using the following instructions to uninstall Anaconda Enterprise, be sure to follow the steps to [backup your current installation](#) so you'll be able to restore your data from the backup after installing Anaconda Enterprise 5.2.

To uninstall Anaconda Enterprise on a healthy cluster worker nodes, run:

```
sudo gravity leave  
sudo killall gravity  
sudo killall planet
```

To uninstall Anaconda Enterprise on a healthy cluster master node, run:

```
sudo gravity system uninstall  
sudo killall gravity  
sudo killall planet  
sudo rm -rf /var/lib/gravity /opt/anaconda
```

To uninstall a failed or faulty cluster node, run:

```
sudo gravity remove --force
```

To remove an offline node that cannot be reached from the cluster, run:

```
sudo gravity remove <node>
```

Where `<node>` specifies the node to be removed. This value can be the node's assigned hostname, its IP address (the one that was used as an "advertise address" or "peer address" during install), or its Kubernetes name (which you can obtain by running `kubectl get nodes`).

1.11 Migrating from AE 4 to AE 5

The process of migrating from AE 4 to AE 5 involves the following tasks:

For Administrators:

- *Export all packages* and package info. from your AE 4 Repository.
- *Import the packages* into Anaconda Enterprise 5.

For Notebook users:

- *Export each project environment* to a `.yaml` file.
- *Convert each project into a format compatible with AE 5.*

- *Upload each project into AE 5.*

Due to architectural changes between versions of the platform, there are some additional steps you may need to follow to *migrate code* between AE4 and AE5. These steps vary, based your current and new platform configurations.

1.11.1 Exporting packages

Anaconda Enterprise enables you to create a site dump of all packages used by your organization, including the owners and permissions associated with each package.

1. Log in to the AE 4 Repo and switch to the `anaconda-server` user.
2. To export your packages, run the following command on the server hosting your Anaconda Repository:

```
anaconda-server-admin export-site
```

Running this command creates a directory structure containing all files and user information from your Anaconda Repository. For example:

```
site-dump/
├── anaconda-user-1
│   ├── 59921152446b5703f430383f--moto
│   ├── 5992115f446b5703fa30383e--pysocks
│   └── meta.json
├── anaconda-organization
│   ├── 5989fbd1446b575b99032652--future
│   ├── 5989fc1d446b575b99032786--iso8601
│   ├── 5989fc1f446b575b990327a8--simplejson
│   ├── 5989fc26446b575b99032802--six
│   ├── 5989fc31446b575b990328b0--xz
│   ├── 5989fc35446b575b990328c6--zlib
│   └── meta.json
└── anaconda-user-2
    └── meta.json
```

Each subdirectory of `site-dump` contains the contents of the Repository *as it pertains to a particular user*. For example `anaconda-user-1` has two packages, `moto` and `pysocks`. The `meta.json` file in each user directory contains information about any groups of end users that user belongs to, as well as their organizations.

Package directories contain the package files, prefixed with the id of the database. The `meta.json` file in each package directory contains metadata about the packages, including version, build number, dependencies, and build requirements.

Note: Other files included in the `site-dump`—such as projects and environments—are NOT imported by the package import tool. That’s why users have to *export their Notebook projects* separately.

1.11.2 Importing packages

You can choose whether to import packages into Anaconda Enterprise 5 by username or organization, or import all packages.

Before you begin:

- We recommend you compare the import options before proceeding, so you can choose the option that most closely aligns with the desired outcome for your organization.

- You'll be using the Anaconda Enterprise command line interface (CLI) to import the packages you exported, so be sure to *install the AE CLI* if you haven't already.

1. Log into the command line interface using the following command:

```
anaconda-enterprise-cli login
```

2. Follow the instructions below for the method you want to use to import packages.

To import packages by username or organization:

As you saw in the example above, the packages for each user are put in a separate directory in the site-dump. This means that the import process is the same whether you specify a directory based on a username or organization.

Import a single directory from the site-dump using the following command:

```
anaconda-enterprise-cli admin import site-dump/name
```

Replacing `name` with the actual name of the directory you want to import.

Note: You can also pass a list of directories to import.

To import all packages:

Run the following command to import all packages in the site dump:

```
anaconda-enterprise-cli admin import site-dump/*
```

How channels of imported packages are named

When you import packages by username, a new channel is created for each unique label the user has applied to their packages, using the username as a prefix. (The default package label “main” is not included in channel names.)

For example, if `anaconda-user-1` has the following packages:

- `moto-0.4.31-2.tar.bz2` with label `main`
- `pysocks-1.6.6-py35_0.tar.bz2` with label `test`

The following channels are created:

- `anaconda-user-1` containing the package file `moto-0.4.31-2.tar.bz2`
- `anaconda-user-1/test` containing the package file `pysocks-1.6.6-py35_0.tar.bz2`

When you import all packages in an organization, a new channel is created for each organization, group, and label. The script appends any groups associated with the organization to the channel name it creates. (The default package label “main” and default organization label “Owner” are not included in channel names.)

For example, if `anaconda-organization` includes a group called `Devs`, and the site dump for `anaconda-organization` contains a package file named `xz-5.2.2-1.tar.bz2` with the label `Test`, running the script will create the following channels:

- `anaconda-organization` – This channel contains all packages that the organization owner can access.
- `anaconda-organization/Devs` – This channel contains all packages that the `Dev` group can access.
- `anaconda-organization/Devs/Test` – This channel contains all packages labeled `Test` that the `Dev` group can access.

Granting access to channels and packages

After everything is uploaded, each channel created as part of the import process is shared with the appropriate users and groups. In the case of the example above, “anaconda-user-1” is granted *read-write* access to the `anaconda-user-1` and `anaconda-user-1/test` channels, and all members of the `Devs` group will have *read* permission for everything in the `Devs` channel.

You can change these access permissions as needed using the Anaconda Enterprise UI or CLI. See [Managing channels and packages](#) for more information.

1.11.3 Migrating AE 4 Notebook Projects

Before you begin:

- If your project refers to channels in your on-premises repository or other channels in `anaconda.org`, ask your System Administrator to [mirror those channels](#) and make them available to you in AE 5.
- If your project use non-conda packages, you’ll need to [upload those packages](#) to AE 5.
- If your notebook refers to multiple kernels or environments, set the kernel to a single environment.
- If your project contains several notebooks, verify that they all are using the same kernel or environment.

1.11.4 Exporting your project

Exporting a project creates a `yml` file that includes all the environment information for the project.

1. Log in to your Anaconda Enterprise Notebooks server.
2. Open a terminal window and activate conda environment 2.6 for your project.
3. Install `anaconda project` in the environment:

```
conda install anaconda-project=0.6.0
```

If you get a `not found` message, install it from `anaconda.org`:

```
conda install -c anaconda anaconda-project=0.6.0
```

4. Export your environment to a file:

```
conda env export -n default -f _env.yml
```

`<default>` is the name of the environment where the notebook runs.

5. Verify that the format of the environment file looks similar to the following, and that the dependencies for each notebook in the project are listed:

```
yml
channels:
- wakari
- r
- https://conda.anaconda.org/wakari
- defaults
- anaconda-adam
prefix: /projects/anaconda/MigrationExample/envs/default
dependencies:
- _license=1.1=py27_1
- accelerate=2.3.1=np111py27_0
- accelerate_cudalib=2.0=0
```

(continues on next page)

(continued from previous page)

```
- alabaster=0.7.9=py27_0
# ... etc ...
```

If it contains any warning messages, run this script to modify the encoding and remove the warnings:

```
import ruamel_yaml
with open("_env.yml") as env_fd:
    env = ruamel_yaml.load(env_fd)
with open("environment.yml", "w") as env_fd:
    ruamel_yaml.dump(env, env_fd, Dumper=ruamel_yaml.RoundTripDumper)
```

1.11.5 Converting your project

To create a project that's compatible with Anaconda Enterprise 5, perform these steps:

1. Run the following command from an interactive shell:

```
anaconda-project init
```

2. AE 4 supports Linux only, so run the following command to remove the Windows and MacOS platforms from the project's `anaconda-project.yml` configuration file:

```
anaconda-project remove-platforms win-64 osx-64
```

3. Run the following command to verify the platforms were removed:

```
anaconda-project list-platforms
```


4. Add `/.indexer.pid` and `.git` to the `.projectignore` file.

5. Run the following command to compress your project:

```
anaconda-project archive FILENAME.tar.gz
```

Note: There is a 1GB file size limit for project files, and project names cannot contain spaces or special characters.

6. In Anaconda Enterprise Notebooks, from your project home page, open the Workbench. Locate your project file (e.g., `AENProject.tar.gz` in the image below) in the file list, right-click and select **Download**.



Now your project is ready to be uploaded into Anaconda Enterprise 5.

1.11.6 Uploading your project to AE 5

Log in to the Enterprise v5 interface and upload your project file `FILENAME.tar.gz`. See *Working with projects* for help.

Note: To maintain performance, there is a 1GB file size limit for project files you upload. Anaconda Enterprise projects are based on Git, so we recommend you commit only text-based files relevant to a project, and keep them under 100MB. Binary files are difficult for version control systems to manage, so we recommend using storage solutions designed for that type of data, and connecting to those data sources from within your Anaconda Enterprise sessions.

1.11.7 Migrating code

AE4 and AE5 are based on a different architecture, therefore some code inside your AE4 notebooks might not run as expected in AE5. AE4 sessions ran directly on the host filesystem, where the libraries, drivers, packages, and connectors required to run them were available. AE5 sessions run in isolated containers with their own independent file system, so they don't necessarily have access to everything on the host.

This difference in architecture primarily impacts the following:

Connecting to external data sources

If you currently rely on ODBC/JDBC drivers to connect to specific databases such as Oracle and Impala, we recommend you use services that support this, such as Apache Impala and Apache Hive, instead. Additionally, using a language and platform agnostic connector such as Thrift allows you to create reproducible code that is more portable.

For best practices on how to connect to different external systems inside AE5, see *Connecting to the Hadoop and Spark ecosystem*.

Service/System	Recommended
Apache Impala	<code>impyla</code>
Apache Hive	<code>pyhive</code>
Oracle	build conda package with their driver

If this is not possible, we recommended you obtain or *build conda packages* for the connectors and drivers you need. This enables you to *add them as package dependencies for your project* that will be installed when you start a Notebook session or deploy the project.

This has the added benefit of enabling you to update dependencies on connectors on a per-project basis.

Sharing custom Python and R libraries

It's quite common to share custom libraries by adding them to a location in the filesystem where all users can access the libraries they need. AE5 sessions and deployments run in isolated containers, so users cannot use this method to access shared libraries.

Instead, we recommend you *create a conda package for each library*. This enables you to control access to each package library and version it—both essential to managing software at the enterprise level.

After you create the package, *upload it to the internal AE5 repository*, where it can be *shared with users* and *included as a dependency* in user sessions and deployments.

Installing external dependencies

If you typically install dependencies using system package managers such as `apt` and `yum`, you can continue to do so in Anaconda Enterprise 5. Dependencies installed from the command line are available during the current session only, however.

If you want them to persist across project sessions and deployments, add them as packages in the project's `anaconda-project.yml` configuration file. See *Configuring project settings* for more information.

If your project depends on package that is not available in your internal Anaconda Enterprise repository, search anaconda.org or build your own conda package using `conda-build` then *upload the conda package* to the AE5 repository.

If you don't have the expertise required to build the custom packages your organization needs, consider *engaging our consulting team* to make your mission-critical analytics libraries available as conda packages.

Administering Anaconda Enterprise

There are several aspects of Anaconda Enterprise that can be configured to meet your organization’s specific requirements, including the following:

- Configuring and monitoring the utilization of *cluster resources*.
- Configuring *user access* to the platform and its resources.
- Configuring *channels* of packages, plus *environments and custom installers* to distribute software.
- Configuring *advanced platform settings*, including *configuring Livy server for Hadoop Spark access*, *configuring external version control*, and *mounting NFS shares*.

Administrators use different consoles to perform tasks in each of these areas, **with credentials required to access each console**. This gives enterprises the flexibility they need to choose whether to grant the permissions required to access a particular console to a single Admin, or different individuals, based on their area(s) of expertise within the organization.

Some configuration options fall outside of these general categories—and you may not necessarily follow this linear process—however, the following offers a high-level overview of the configuration workflow you’re likely to follow:




2.1 Managing cluster resources

After you've *installed an Anaconda Enterprise cluster*, you'll want to continue to manage and monitor the cluster to ensure that it scales with your organization as needs change. These on-going management and monitoring tasks include the following:

- When you've outgrown your initial Anaconda Enterprise cluster installation,

you can easily *add new nodes*—including GPUs. To make these nodes available to platform users, you'll *configure resource profiles*.

- To help you manage your organization's cluster resources more efficiently, Anaconda Enterprise enables you to *track which sessions and deployments are running on specific nodes or by specific users*. You can also *monitor cluster resource usage* in terms of CPU, memory, disk space, network and GPU utilization.
- To help you gain insights into user services and troubleshoot issues, Anaconda Enterprise provides *detailed logs* and debugging information related to the Kubernetes services it uses, as well as all *activity performed by users*. See *fault tolerance in Anaconda Enterprise* for information about what to do if a master node fails.



2.1.1 Adding and removing nodes


You can view, add, edit and delete server nodes from Anaconda Enterprise using the Admin Console's Operations Center. If you would prefer to use a command line to join additional nodes to the AE master, follow *the instructions provided below*.

NOTES:

- Each installation can only support a single AE master node, as this node includes storage for the platform. **DO NOT add an additional AE master node to your installation.**
- As a best practice for etcd optimal cluster size, we recommend you **add any additional Kubernetes master nodes in pairs**, so that the total number (including the AE master) is an odd number.
- Anaconda Enterprise doesn't support running heterogeneous versions in the same cluster. Before adding a new node, *verify that the node is operating the same version of the OS as the rest of the cluster.*


- If you're adding a GPU node, make sure it meets the *GPU requirements*.

To manage the servers on your system:

1. Log in to Anaconda Enterprise, select the **Menu** icon  in the top right corner and click the **Administrative Console** link displayed at the bottom of the slide out window. You must be logged in with a user assigned to the `ae-admin` role.
2. Click **Manage Resources**.
3. Log in to the Operations Center using the Administrator credentials *configured after installation*.
4. Select **Nodes** from the menu on the left to display the configured nodes in your cluster, their IP address, hostname and profile.

To add an existing server to Anaconda Enterprise:


1. Click the **Add Node** button at the top right.





2. Select an appropriate profile for the server and click **Continue**.
3. Copy and paste the command provided into a terminal window to add the server.


When you refresh the page, your server will appear in the list.


To remove a server node:

Click the Actions menu  at the far right of the node you want to remove and select **Delete...**

**To log on to a server:**

Click on the terminal icon  of the server you want to work with, and select **root** to open a terminal window. It will open a new tab in your browser.



When you are finished, simply close the console window by clicking the  icon.

Using the command line to add nodes


1. Download the gravity binary that corresponds to your version of Anaconda Enterprise from the S3 location provided to you by Anaconda onto the server you're adding to the cluster.
2. Rename the file to something simpler, then make it executable. For example:


```
mv gravity-binary-6.1.9 gravity
chmod +x gravity
```

3. *On the AE master*, run the following command to obtain the join token and IP address for the AE master node:

```
gravity status
```

The results should look similar to the following:



```
Cluster status:      active
Application:        AnacondaEnterprise, version 5.4.0-36.gdf45da616
Join token:         9954bf9f357b0eff8d2d2a4a48c8d9e6
Periodic updates:   Not Configured
Remote support:     Not Configured
Last completed operation:
  * operation_install (9c1bc3ec-4ff4-4069-8096-9be6ac28960c)
    started:         Tue Oct 29 14:25 UTC (45 minutes ago)
    completed:       Tue Oct 29 14:39 UTC (32 minutes ago)
Cluster endpoints:
  * Authentication gateway:
    - 172.31.67.113:32009
  * Cluster management URL:
    - https://172.31.67.113:32009
Cluster nodes:      test-install.training.anaconda.com
Masters:
  * ip-172-31-67-113.ec2.internal / 172.31.67.113 / ae-master
    Status:          healthy
```

Join Token

Master IP Address

4. Copy and paste the join token for the cluster and the IP address for the AE master somewhere accessible. You'll need to provide this information when you add a new worker node. You'll also need the IP address of the server node you're adding.
5. *On the worker node*, run the following command to add the node to the cluster:

```
./gravity join --token JOIN-TOKEN --advertise-addr=NODE-IP --role=NODE-ROLE --
--cloud-provider=CLOUD-PROVIDER MASTER-IP-ADDR
```

Where:

JOIN-TOKEN = The join token that you obtained in Step 3.

NODE-IP = The IP address of the worker node. This can be a private IP address, as long as the network it's on can access the AE master.

NODE-ROLE = The type of node you're adding: `ae-worker`, `gpu-worker`, or `k8s-master`.

CLOUD-PROVIDER = This is auto-detected, and can therefore be excluded unless you don't have Internet access. In this case, use `generic`.

MASTER-IP-ADDR = The IP address of the AE master that you obtained in Step 3.

Warning: The `--role` flag must be provided and assigned to either `ae-worker`, `gpu-worker` or `k8s-master`. Without it the node will be added with the role `ae-master` and may cause your cluster to crash.

The progress of the join operation is displayed:

```
[root@atk-worker ~]# ./gravity join --token 24f51901025ebaa3e3e38db5767d3809751d9e40a6b4013089fe064658f56970 --advertise-addr=10.200.30.180 --role=ae-worker 10.200.30.165
Tue Nov 27 17:27:24 UTC Joining cluster
Tue Nov 27 17:27:24 UTC Connecting to cluster
Tue Nov 27 17:27:24 UTC Connected to existing cluster at 10.200.30.165
Tue Nov 27 17:27:26 UTC Operation has been created
Tue Nov 27 17:27:27 UTC Running preflight checks
Tue Nov 27 17:27:28 UTC Configuring system packages
Tue Nov 27 17:27:32 UTC Installing software
Tue Nov 27 17:42:56 UTC Registering with Kubernetes
Tue Nov 27 17:42:57 UTC Updating Kubernetes node labels
[root@atk-worker ~]#
```

- To monitor the impact of the join operation on the cluster, run the `gravity status` command *on the AE master*.

The output will look similar to the following:

```
Cluster status:      expanding
Application:         AnacondaEnterprise, version 5.4.0-36.gdf45da616
Join token:          9954bf9f357b0eff8d2d2a4a48c8d9e6
Periodic updates:    Not Configured
Remote support:      Not Configured
Active operations:
  * operation_expand (27542137-ee9d-492c-8749-0f06fd878fd6)
    started: Tue Oct 29 16:09 UTC (7 seconds ago)
    Pull packages on the joining node, 20% complete
Last completed operation:
  * operation_install (9c1bc3ec-4ff4-4069-8096-9be6ac28960c)
    started: Tue Oct 29 14:25 UTC (1 hour ago)
    completed: Tue Oct 29 14:39 UTC (1 hour ago)
Cluster endpoints:
  * Authentication gateway:
    - 172.31.67.113:32009
  * Cluster management URL:
    - https://172.31.67.113:32009
Cluster nodes: test-install.training.anaconda.com
Masters:
  * ip-172-31-67-113.ec2.internal / 172.31.67.113 / ae-master
    Status: healthy
Nodes:
  * ip-172-31-72-9.ec2.internal / 172.31.72.9
    Status: offline
```

Note that the size of the cluster is `expanding` and the status of the new node being added is `offline`. When the node has successfully joined, the cluster returns to an `active` state, and the status of the new node changes to `healthy`:

```
Cluster status:      active
Application:         AnacondaEnterprise, version 5.4.0-36.gdf45da616
Join token:          9954bf9f357b0eff8d2d2a4a48c8d9e6
Periodic updates:    Not Configured
Remote support:      Not Configured
Last completed operation:
  * operation_expand (27542137-ee9d-492c-8749-0f06fd878fd6)
    started: Tue Oct 29 16:09 UTC (4 minutes ago)
    completed: Tue Oct 29 16:11 UTC (2 minutes ago)
Cluster endpoints:
  * Authentication gateway:
    - 172.31.67.113:32009
  * Cluster management URL:
    - https://172.31.67.113:32009
Cluster nodes: test-install.training.anaconda.com
Masters:
  * ip-172-31-67-113.ec2.internal / 172.31.67.113 / ae-master
    Status: healthy
Nodes:
  * ip-172-31-72-9.ec2.internal / 172.31.72.9 / ae-worker
    Status: healthy
```

2.1.2 Setting resource limits for sessions and deployments

Note: You can separate system-level pods from user-level sessions and deployments as long as you have a multi-node setup (that is, a master node and at least one worker node). Contact support to complete this operation.


Each project editor session and deployment uses compute resources on the Anaconda Enterprise cluster. If Anaconda Enterprise users need to run applications which require more memory or compute power than provided by default, you can customize your installation to include these resources and allow users to access them while working within AE.


After the server resources are installed as nodes in the cluster, you create custom *resource profiles* to configure the number of cores and amount of memory/RAM available to users—so that it corresponds to your specific system configuration and the needs of your users.

For example, if your installation includes nodes with GPUs, add a GPU resource profile so users can use the GPUs to accelerate computation within their projects—essential for machine learning model training. For installation requirements, see [Installation requirements](#).

Resource profiles apply to all nodes, users, editor sessions, and deployments in the cluster. So if your installation includes nodes with GPUs that you want to make available for users to accelerate computation within their projects, you'd create a GPU resource profile. Any resource profiles you configure are listed for users to select from when [configuring a project](#) and [deploying a project](#). Anaconda Enterprise finds the node that matches their request.

To add a resource profile for a resource you have installed:


1. Log in to Anaconda Enterprise, select the **Menu** icon  in the top right corner and click the **Administrative Console** link displayed at the bottom of the slide out window.
2. Click **Manage Resources**.
3. Log in to the Operations Center using the Administrator credentials [configured after installation](#).
4. Select **Configuration** from the menu on the left.
5. Use the **Config map** drop-down menu to select the `anaconda-enterprise-anaconda-platform.yml` configuration file.
6. **Make a manual backup copy of this file before editing it**, as any changes you make will impact how Anaconda Enterprise functions.
7. Scroll down to the `resource-profiles` section:



8. Add an additional resource following the format of the default specification. For example, to create a GPU resource profile, add the following to the `resource-profiles` section of the Config map:

```
gpu-profile:
  description: 'GPU resource profile'
  user_visible: true
  resources:
    limits:
      cpu: '4'
      memory: '8Gi'
      nvidia.com/gpu: 1
```

By default, CPU sessions and deployments are also allowed to run on GPU nodes. *To reserve GPU nodes for only those sessions and deployments that require a GPU*—by preventing CPU sessions and deployments from accessing GPU nodes—comment out the following additional specification included after the `gpu-profile` entry:

A screenshot of a code editor showing the configuration file `anaconda-enterprise-anaconda-platform.yml`. The file contains a section for `affinity` with a `nodeAffinity` block. The `nodeAffinity` block has a `requiredDuringSchedulingIgnoredDuringExecution` section with a `nodeSelectorTerms` list. The first term has a `matchExpressions` list with one expression: `key: gpu`, `operator: NotIn`, and `values: - 'true'`. The second term has a `matchExpressions` list with one expression: `key: gpu`, `operator: NotIn`, and `values: - 'true'`. The `weight` is set to 100. The code is displayed in a dark-themed editor with line numbers on the left.

```
102
103 ## Section affinity is used to specify whether user CPU session/deployment/job/cronjob
104 ## should run on GPU node. User can configure it as hard requirement --
105 ## requiredDuringSchedulingIgnoredDuringExecution or soft requirement --
106 ## preferredDuringSchedulingIgnoredDuringExecution. It is soft requirement by default.
107 ## Please follow sample configuration below.
108
109 # affinity:
110 #   nodeAffinity:
111 #     requiredDuringSchedulingIgnoredDuringExecution:
112 #       nodeSelectorTerms:
113 #         - matchExpressions:
114 #           - key: gpu
115 #             operator: NotIn
116 #             values:
117 #               - 'true'
118 #####
119 affinity:
120   nodeAffinity:
121     preferredDuringSchedulingIgnoredDuringExecution:
122     - preference:
123         matchExpressions:
124         - key: gpu
125           operator: NotIn
126           values:
127             - "true"
128       weight: 100
129
```

Note: Resource profiles are listed in alphabetical order—after any defaults—so if you want them to appear in a particular order in the drop-down list that users see, be sure to name them accordingly.

9. Click **Apply** to save your changes.

To update the Anaconda Enterprise server with your changes, you'll need to do the following:

Restart the workspace and deploy services by running the following command:


```
kubectl delete pods -l 'app in (ap-workspace, ap-deploy)'
```

Then check the project **Settings** and **Deploy** UI to verify that each resource profile you added or edited appears in the **Resource Profile** drop-down menu.

2.1.3 Monitoring cluster utilization


Anaconda Enterprise enables you to monitor cluster resource usage in terms of CPU, memory, disk space, network and GPU utilization.

To access the Operations Center:

1. Log in to Anaconda Enterprise, select the **Menu** icon  in the top right corner and click the **Administrative Console** link displayed at the bottom of the slide out window.
2. Click **Manage Resources**.
3. Log in to the Operations Center using the Administrator credentials *configured after installation*


Total cluster resource utilization

The **Dashboard** tab in the Operations Center displays the total CPU and Memory utilize aggregated across all nodes (master and worker) nodes in the Anaconda Enterprise cluster.



Monitoring dashboard

4. Click **Monitoring** in the menu on the left.



The graphs displayed include the following:

- Overall Cluster CPU Usage
- CPU Usage by Node
- Individual CPU Usage
- Overall Cluster Memory Usage
- Memory Usage by Node
- Individual Node Memory Usage
- Overall Cluster Network Usage
- Network Usage by Node
- Individual Node Network Usage
- Overall Cluster Filesystem Usage
- Filesystem Usage by Node
- Individual Filesystem Usage

Use the control in the upper right corner to specify the range of time for which you want to view usage information, and how often you want to refresh the results.

The screenshot shows a control panel for time ranges and refresh rates. At the top, there is a dropdown menu set to 'Last 1 hour' and a 'Refresh every 10s' button. Below this is a 'Quick ranges' section with a grid of time-based options. The 'Last 1 hour' option is currently selected. Below the quick ranges is a 'Custom range' section with input fields for 'From:' (set to 'now-1h') and 'To:' (set to 'now'), and a 'Refreshing every:' dropdown set to '10s'. An 'Apply' button is located at the bottom right of the custom range section.

Quick ranges			
Last 2 days	Yesterday	Today	Last 5 minutes
Last 7 days	Day before yesterday	Today so far	Last 15 minutes
Last 30 days	This day last week	This week	Last 30 minutes
Last 90 days	Previous week	This week so far	<u>Last 1 hour</u>
Last 6 months	Previous month	This month	Last 3 hours
Last 1 year	Previous year	This month so far	Last 6 hours
Last 2 years		This year	Last 12 hours
Last 5 years		This year so far	Last 24 hours

Custom range

From: now-1h

To: now


Refreshing every: 10s

Apply

Monitoring Kubernetes

To view the status of your Kubernetes nodes, pods, services, jobs, daemon sets and deployments from the Operations Center, click **Kubernetes** in the menu on the left and select **Pods**.


See *Monitoring sessions and deployments* for more information.




To view the status or progress of a cluster installation, click **Operations** in the menu on the left, and select an operation in the list. Clicking on a specific operation switches to the **Logs** view, where you can also view logs based on container or pod.

2.1.4 Monitoring sessions and deployments

Anaconda Enterprise enables you to see which sessions and deployments are running on specific nodes or by specific users, so you can monitor cluster resource usage. You can also view session details *for a specific user* in the Authorization Center. See [Managing users](#) for more information.

1. Log in to Anaconda Enterprise, select the **Menu** icon  in the top right corner and click the **Administrative Console** link displayed at the bottom of the slide out window.
2. Click **Manage Resources**.
3. Log in to the Operations Center using the Administrator credentials *configured after installation*.
4. Select **Monitoring** from the menu on the left to display the monitoring dashboards.




Individual pod

To display the monitoring graph for a user session or deployment you'll need to identify the appropriate Kubernetes pod name.


For an editor session the Kubernetes pod name corresponds to the hostname of the session container. Run `hostname` in a terminal window. For deployments the pod name is available from the logs tab of the deployment under the heading **name**.

1. Click the **Monitoring** tab from the menu on the left
2. Click **Cluster** at the top left of the dashboard
3. Select **Compute Resource / Workload**




To display the monitoring graph for an individual pod

1. Select `default` from the **namespace** menu
2. Select the desired pod from the the **workload** menu



Scroll down further to display the memory usage.



Using the CLI:

Note: For more expanded monitoring, see [AE5 Tools](#).

1. Open an SSH session on the master node in a terminal by logging into the Operations Center and selecting **Servers** from the menu on the left.
2. Click on the IP address for the Anaconda Enterprise master node and select SSH login as **root**.
3. In the terminal window, run `sudo gravity enter`.

To view total node CPU and memory utilization run

```
kubectl top nodes --heapster-namespace=monitoring
```


To view CPU and memory utilization per pod run


```
kubectl top pods --heapster-namespace=monitoring
```

2.1.5 Viewing system logs

To help you gain insights into user services and troubleshoot issues, Anaconda Enterprise provides detailed logs and debugging information related to the Kubernetes services and containers it uses.

To access these logs from the Operations Center:

1. Log in to Anaconda Enterprise, select the **Menu** icon  in the top right corner and click the **Administrative Console** link displayed at the bottom of the slide out window.
2. Click **Manage Resources**.
3. Log in to the Operations Center using the Administrator credentials *configured after installation*.
4. Click **Logs** in the left menu to display the complete system log.
5. Use the **Filter** drop-down to view logs based on a container.




Note: You can also access the logs for a specific pod by clicking **Kubernetes** in the left menu, clicking the **Pods** tab, clicking the name of a pod, and selecting **Logs**.

Individual pods

To display the logs for a user session or deployment you'll need to identify the appropriate Kubernetes pod name.

For an editor session the Kubernetes pod name corresponds to the hostname of the session container. Run `hostname` in a terminal window. For deployments the pod name is available from the logs tab of the deployment under the heading **name**.

1. Click the **Kubernetes** tab from the menu on the left
2. Click the **Pods** tab to display a list of all pods and containers. Editor sessions are named `anaconda-session-XXXXX` and deployments are named `anaconda-app-XXXX`.



1. For the chosen pod click the pull-down button on an individual container to view the **Logs** or to gain SSH access.



To use the CLI:

1. Open an SSH session on the master node in a terminal by logging into the Operations Center and selecting **Servers** from the menu on the left.
2. Click on the IP address for the Anaconda Enterprise master node and select SSH login as **root**.
3. In the terminal window, run `sudo gravity enter`.
4. Run `kubectl get pods` to view a list of all running session pods.
5. Run `kubectl logs <POD-NAME>` to display the logs for the pod specified.


2.1.6 Viewing activity logs

Anaconda Enterprise logs all activity performed by users, including the following:

- Each system login.
- All Admin actions.
- Each time a project is created and updated.
- Each time a project is deployed.

In each case, the user who performed the action and when it occurred are tracked, along with any other important details.

As an Administrator, you can log in to the Administrative Console's Authentication Center to view the log of all login and Admin events:

1. Log in to Anaconda Enterprise, select the **Menu** icon  in the top right corner and click the **Administrative Console** link displayed at the bottom of the slide out window.
2. Click **Manage Users**.
3. Log in to the Authentication Center using the Administrator credentials required to access it.
4. Click **Events** in the left menu to display a log of all **Login Events**.
5. Click the **Admin Events** tab to view a summary of all actions performed by Admin users.

To filter events:

Event data can become difficult to manage as it accumulates, so Anaconda Enterprise provides a few options to make it more manageable:

1. Click the **Config** tab to configure the type of events you want Anaconda Enterprise to log, clear events, and schedule if you want to periodically delete event logs from the database.
2. Use the **Filter** options available on both the **Login Events** and **Admin Events** windows to control the results displayed based on variables such as event or operation, user or resource, and a range of dates.



- Click **Update** to refresh the results based on the filter you configured, and **Reset** to return to the original log results.
- Select the maximum number of results you want displayed: 5, 10, 50 or 100.

To view activity at the project level:

1. Switch to the User Console and click **Projects** in the top menu.
2. Select the project you want to view information about to display a list of all actions performed on the project in the **Activity** window.

2.1.7 Fault tolerance in Anaconda Enterprise

Anaconda Enterprise employs automatic service restarts and health monitoring to remain operational if a process halts or a worker node becomes unavailable. Additional levels of fault tolerance, such as service migration, are provided if there are *at least three nodes* in the deployment. However, the master node cannot currently be configured for automatic failover and does present a single point of failure.

When Anaconda Enterprise is deployed to a cluster with *three or more nodes*, the core services are automatically configured into a fault tolerant mode—whether Anaconda Enterprise is initially configured this way or changed later. As soon as there are three or more nodes available, the service fault tolerance features come into effect.

This means that in the event of any service failure:

- Anaconda Enterprise core services will automatically be restarted or, if possible, migrated.
- User-initiated project deployments will automatically be restarted or, if possible, migrated.

If a *worker node* becomes unresponsive or unavailable, it will be flagged while the core services and backend continue to run without interruption. If additional worker nodes are available the services that had been running on the failed worker node will be migrated or restarted on other still-live worker nodes. This migration may take a few minutes.

The process for adding new worker nodes to the Anaconda Enterprise cluster is described in [Adding and removing nodes](#).

Storage and persistency layer

Anaconda Enterprise does not automatically configure storage or persistency layer fault tolerance when using the default storage and persistency services. This includes the database, Git server, and object storage. If you have configured Anaconda Enterprise to use external storage and persistency services then you will need to configure these for fault tolerance.

Recovering after node failure

Other than storage-related services (database, Git server, and object storage), all core Anaconda Enterprise services are resilient to master node failure.

To maintain operation of Enterprise in the event of a master node failure, `/opt/anaconda/` on the master node should be located on a redundant disk array or backed up frequently to avoid data loss. See [Backing up and restoring AE](#) for more information.

To restore Anaconda Enterprise operations in the event of a master node failure:

1. Create a new master node. Follow the installation process for adding a new cluster node, described in [command-line installations](#).

Note: To create the new master node, select `--role=ae-master` instead of `--role=ae-worker`.


2. Restore data from a backup. After the installation of the new master node is complete, follow the instructions in [Backing up and restoring AE](#).

2.2 Configuring user access

As an Administrator, you'll need to authorize users so they can use Anaconda Enterprise. This involves [adding users to the system](#), setting their credentials, [mapping them to roles](#), and optionally [assigning them to one or more groups](#).

To help expedite the process of authorizing large groups of users, you can [connect to an external identity provider](#) such as LDAP or Active Directory and federate those users.

You'll need access to the Administrative Console's Authentication Center to be able to use it to configure identity and access management for Anaconda Enterprise. Follow [these instructions](#) to grant Admins permission to manage AE users.




2.2.1 Connecting to external identity providers


Anaconda Enterprise comes with out-of-the-box support for LDAP, Active Directory, SAML and Kerberos. As each enterprise configuration is different, coordinate with your LDAP/AD Administrator to obtain the provider-specific information you need to proceed. We've also provided an [example of an LDAP setup](#) to help guide you through the process.

Note: You must have pagination turned off before starting.

Adding a provider

You'll use the Administrative Console's Authentication Center to add an identity provider:

1. Login to Anaconda Enterprise, click the **Menu** icon  in the top right corner, then click the **Administrative Console** link in the bottom of the slideout menu.
2. Click **Manage Users**.
3. Login to the Authentication Center using the Administrator credentials required to access it.



4. In the Configure menu on the left, select **User Federation**.
5. Select `ldap` from the Add provider selector to display the initial **Required Settings** screen.

Multiple fields are required. The most important is the **Vendor** drop-down list, which will prefill default settings based on the LDAP provider you select. Make sure you select the correct one: `Active Directory`, `Red Hat Directory Server`, `Tivoli`, or `Novell eDirectory`. If none of these matches, select `Other` and coordinate with your LDAP Administrator to provide values for the required fields:

Username LDAP attribute Name of the LDAP attribute that will be mapped to the username. Active Directory installations may use `cn` or `sAMAccountName`. Others often use `uid`.

RDN LDAP attribute Name of the LDAP attribute that will be used as the RDN for a typical user DN lookup. This is often the same as the above “Username LDAP attribute”, but does not have to be. For example, Active Directory installations may use `cn` for this attribute while using `sAMAccountName` for the “Username LDAP attribute”.

UUID LDAP attribute Name of an LDAP attribute that will be unique across all users in the tree. For example, Active Directory installations should use `objectGUID`. Other LDAP vendors typically define a UUID attribute, but if your implementation does not have one, any other unique attribute (such as `uid` or `entryDN`) may be used.

User Object Classes Values of the LDAP `objectClass` attribute for users, separated by a comma. This is used in the search term for looking up existing LDAP users, and if read-write sync is enabled, new users will be added to LDAP with these `objectClass` values as well.

Connection URL The URL used to connect to your LDAP server. Click **Test connection** to make sure your connection to the LDAP server is configured correctly.

Users DN The full DN of the LDAP tree—the parent of LDAP users. For example, `'ou=users,dc=example,dc=com'`.

Authentication Type The LDAP authentication mechanism to use. The default is `simple`, which requires the Bind DN and password of the LDAP Admin.

Bind DN The DN of the LDAP Admin, required to access the LDAP server.

Bind Credential The password of the LDAP Admin, required to access the LDAP server. After supplying the DN and password, click **Test authentication** to confirm that your connection to the LDAP server can be authenticated.

Configuring sync settings

By default, users will not be synced from the LDAP / Active Directory store until they log in. If you have a large number of users to import, it can be helpful to set up batch syncing and periodic updates.

Sync Settings

Batch Size

Periodic Full Sync ☐ OFF

Periodic Changed Users Sync ☐ OFF

Configuring mappers

After you complete the initial setup, the auth system generates a set of “mappers” for your configuration. Each mapper takes a value from LDAP and maps it to a value in the internal auth database.

Ldap

Settings Mappers

Search...

Name	Type
username	user-attribute-ldap-mapper
first name	user-attribute-ldap-mapper
last name	user-attribute-ldap-mapper
email	user-attribute-ldap-mapper
creation date	user-attribute-ldap-mapper
modify date	user-attribute-ldap-mapper

Go through each mapper and make sure it is set up appropriately.

- Check that each mapper reads the correct “LDAP attribute” and maps it to the right “User Model Attribute”.
- Check that the attribute’s “read-only” setting is correct.
- Check whether the attribute should always be read from the LDAP store and not from the internal database.

For example, the `username` mapper sets the Anaconda Enterprise username from the LDAP attribute configured.

Configuring advanced mappers

Instead of manually configuring each user, you can automatically import user data from LDAP using additional mappers. The following mappers are available:

User Attribute Mapper (`user-attribute-ldap-mapper`) Maps LDAP attributes to attributes on the AE5 user. These are the default mappers set up in the initial configuration.

Username

ID

Name *

Mapper Type

User Model Attribute

LDAP Attribute

Read Only ☒ ON ☐ OFF

Always Read Value From LDAP ☐ OFF

Is Mandatory In LDAP ☒ ON ☐ OFF

Is Binary Attribute ☐ OFF

FullName Mapper (`full-name-ldap-mapper`) Maps the full name of the user from LDAP into the internal database.

Role Mapper (`role-ldap-mapper`) Sets role mappings from LDAP into realm role mappings. One role mapper can be used to map LDAP roles (usually groups from a particular branch of an LDAP tree) into realm roles with corresponding names.

Multiple role mappers can be configured for the same provider. It's possible to map roles to a particular client (such as the `anaconda-deploy` service), but it's usually best to map in realm-wide roles.

Hardcoded Role Mapper (`hardcoded-ldap-role-mapper`) Grants a specified role to each user linked with LDAP.

Hardcoded Attribute Mapper (`hardcoded-ldap-attribute-mapper`) Sets a specified attribute to each user linked with LDAP.

Group Mapper (`group-ldap-mapper`) Sets group mappings from LDAP. Can map LDAP groups from a branch of an LDAP tree into groups in the Anaconda Platform realm. It will also propagate user-group membership from LDAP. We generally recommend using roles and not groups, so the role mapper may be more useful.

Warning: The group mapper provides a setting `Drop non-existing groups during sync`. If this setting is turned on, existing groups in Anaconda Enterprise Authentication Center will be erased.

MSAD User Account Mapper (`msad-user-account-control-mapper`) Microsoft Active Directory (MSAD) specific mapper. Can tightly integrate the MSAD user account state into the platform account state, including whether the account is enabled, whether the password is expired, and so on. Uses the `userAccountControl` and `pwdLastSet` LDAP attributes.

For example if `pwdLastSet` is 0, the user is required to update their password and there will be an `UPDATE_PASSWORD` required action added to the user. If `userAccountControl` is 514 (disabled account), the platform user is also disabled.

Mapper configuration example

To map LDAP group membership to Anaconda Platform roles, use a role mapper.

Add a mapper of the `role-ldap-mapper` type:

Add user federation mapper

Name *

Mapper Type

- msad-user-account-control-mapper
- msad-ids-user-account-control-mapper
- group-ldap-mapper
- user-attribute-ldap-mapper
- role-ldap-mapper
- hardcoded-ldap-role-mapper
- full-name-ldap-mapper
- hardcoded-ldap-attribute-mapper

In consultation with your LDAP administrator and internal LDAP documentation, define which LDAP group tree will be mapped into roles in the Anaconda Platform realm. The roles are mapped directly by name, so an LDAP membership of `ae-deployer` will map to the role of the same name in Anaconda Platform.

Add user federation mapper

Name *

Mapper Type

LDAP Roles DN

Role Name LDAP Attribute

Role Object Classes

Membership LDAP Attribute

Membership Attribute Type

Membership User LDAP Attribute

LDAP Filter

Mode

User Roles Retrieve Strategy

Use Realm Roles Mapping

Client ID

Authorizing LDAP groups and roles

To authorize LDAP group members or roles synced from LDAP to perform various functions, add them to the `anaconda-enterprise-anaconda-platform.yml` configmap.

EXAMPLE: To give users in the LDAP group “AE5”, and users with the LDAP-synced role “Publisher”, permission to deploy apps, the deploy section would look like this:

```
deploy:
  port: 8081
  prefix: '/deploy'
  url: https://abc.demo.anaconda.com/deploy
  https:
    key: /etc/secrets/certs/privkey.pem
    certificate: /etc/secrets/certs/cert.pem
  hosts:
    - abc.demo.anaconda.com
  db:
    database: anaconda_deploy
  users: '*'
```

(continues on next page)

(continued from previous page)

```
deployers:
  users: []
  groups:
    - developers
    - AE5
  roles:
    - Publisher
```

After editing the configmap, restart all pods for your changes to take effect:

```
kubect1 get pods | grep ap- | cut -d' ' -f1 | xargs kubect1 delete pods
```

Configuring LDAPS (Outbound SSL)

To make correct requests to secure internal resources such as internal enterprise LDAP servers using corporate SSL certificates, you must configure a “trust store”. *This is optional*. If your internal servers instead use certificates issued by a public root CA, then the default trust store is sufficient.

To create a trust store, you must have the public certificates you wish to trust available.

Note: These are certificates for your **trusted server** such as Secure LDAP, *not* for Anaconda Enterprise.

Option 1

If the CA certificates are directly available to you, run the following command, replacing `CAFILE.cert` with your CA certificate file:

```
keytool -import -file CAFILE.cert -alias auth -keystore LDAPS.jks
```

Note: If you want to add an intermediate certificate, run this command again **with a unique alias**, to include it in the `LDAPS.jks` file.

Option 2

Alternatively, if you also have the server certificate and key, you can construct a full trust chain in the store.

1. Convert the certificate and key files to PKCS12 format—if they are not already—by running the following command:

```
openssl pkcs12 -export -chain -in CERT.pem -inkey CERT-KEY.pem -out PKCS-CHAIN.
↪p12 -name auth -CAfile CA-CHAIN.pem
```

In this example, replace `CERT.pem` with the server’s certificate, `CERT-KEY.pem` with the server’s key, `PKCS-CHAIN.p12` with a temporary file name, and `CA-CHAIN.pem` with the trust chain file (up to the root certificate of your internal CA).

2. Create a Java keystore to store the trusted certs:

```
keytool -importkeystore -destkeystore LDAPS.jks -srckeystore PKCS-CHAIN.p12 -
↳alias auth
```

3. You will be prompted to set a password. Record the password.

Final steps

For both options, you'll need to follow the steps below to expose the certificates to the Anaconda Enterprise Auth service:

1. Export the existing SSL certificates for your system by running the following commands:

```
sudo gravity enter
kubectl get secrets anaconda-enterprise-certs --export -o yaml > /opt/anaconda/
↳secrets-exported.yaml
```

2. Exit the gravity environment, and back up the secrets file before you edit it:

```
cp secrets-exported.yaml secrets-exported-orig.yaml
```

3. Run the following command to encode the newly created truststore as base64:

```
echo "  ldaps.jks: '$(base64 -i --wrap=0 OUTPUT.jks)'
```


4. Copy the output of this command, and paste it into the data section of the `secrets-exported.yaml` file.
5. Run the following commands to update Anaconda Enterprise with the secrets certificate:

```
sudo gravity enter
kubectl replace -f /opt/anaconda/secrets-exported.yaml
```

6. Verify that the `LDAPS.jks` entry has been added to the secret:

```
kubectl describe secret anaconda-enterprise-certs
```

7. *Edit the platform configuration* by setting the `auth.https.truststore` configuration key to `/etc/secrets/certs/ldaps.jks`, and `auth.https.truststore-password` to the matching password. For example, after editing, it should resemble the following:



The screenshot shows the Anaconda Enterprise configuration interface. On the left is a sidebar with navigation links: Admin, Servers, Operations, Logs, Monitoring, Kubernetes, and Configuration. The main panel displays the configuration for 'anaconda-enterprise-anaconda-...' with a 'Config maps' section. The selected config map is 'anaconda-platform.yaml'. The configuration content is as follows:

```
# PER-SERVICE CONFIGURATION
# =====
# CONFIGURABLE SECTION:
# =====
# auth.https.keystore: Name of server keystore in Java keystore (.jks) format
# auth.https.keystore-password: Keystore password defined when generating the Java keystore
# auth.https.key-alias: Name of the key in the keystore
# auth.https.truststore: Optional. Path to the trust store to use for outgoing HTTPS requests (e.g. for LDAPS)
# auth.https.truststore-password: Optional. Truststore password defined when generating the Java keystore
# =====
auth: # Authentication server configuration
  port: 8888
  db:
    database: anaconda_auth
    https: # HTTPS configuration
      key-alias: auth
      keystore: /etc/secrets/certs/keystore.jks
      keystore-password: anaconda
      truststore: /etc/secrets/certs/ldaps.jks
      truststore-password: anaconda

  debug: False # If true, enable use of a pregenerated SSL key for testing. DO NOT SET TO TRUE IN PRODUCTION.
  import-file: /etc/secrets/keys/anaconda.key
  api: # Service settings for auth-api
    port: 9080
    listen: 12
    prefix: /platform/auth-api
    https:
      key: /etc/secrets/certs/tls.key
      certificate: /etc/secrets/certs/tls.crt
    escrow: # Service settings for auth-escrow
      port: 9091
      db:
        database: anaconda_auth_escrow
        hosts: # List of hosts (host:port pairs) to allow in API request headers
          - name=S3-master-1.cdev.anaconda.com
          prefix: /platform/auth-escrow
      https:
        key: /etc/secrets/certs/tls.key
        certificate: /etc/secrets/certs/tls.crt
```

8. Run the following commands to restart the auth service:

```
sudo gravity enter
kubectl get pods | grep ap-auth | cut -d' ' -f1 | xargs kubectl delete pods
```


2.2.2 Managing users


Managing access to Anaconda Enterprise involves adding and removing users, setting passwords, *mapping users to roles, and optionally assigning them to groups*. To help expedite the process of authorizing large groups of users at once, you can *connect to an external identity provider* using LDAP, Active Directory, SAML, or Kerberos to federate those users.

Note: To be able to perform these actions, you'll need the appropriate login credentials required to access the Administrative Console's Authentication Center.


The process of authorizing Operations Center Admins is slightly different. See *Managing System Administrators* for more information.

To access the Authentication Center:

1. Login to Anaconda Enterprise, click the **Menu** icon  in the top right corner, then click the **Administrative Console** link in the bottom of the slideout menu.
2. Click **Manage Users**.
3. If this is the first time accessing the Authentication Center, log in using the default `admin` credentials. Otherwise, use the credentials that grant you Admin privileges in the Authentication Center.



Note: To create and manage other Authentication Center Admins, use the realm selector in the upper left corner to switch to the **Master** realm before proceeding.



4. In the Manage menu on the left, click **Users**.
5. On the **Lookup** tab, click **View all users** to list every user in the system, or search the user database for all users that match the criteria you enter, based on their first name, last name, or email address.


Note: This will search the local user database and not the federated database (such as LDAP) because not all external identity provider systems include a way to page through users. If you want users from a federated database to be synced into the local database, select **User Federation** in the Configure menu on the left, and adjust the **Sync Settings** for your user federation provider.

6. **To create a new Anaconda Enterprise user**, click **Add user** and specify a user name—and optionally provide values for the other fields—before clicking **Save**.

Warning: User names containing unicode characters—special characters, punctuation, symbols, spaces—are not permitted.


7. **To configure a user**, click the user's ID in the list and use the available tabs as follows:
 - Use the **Details** tab to specify information for the user, optionally enable *user registration* and *required actions* and *impersonate the user*. If you include an email address, an invitation to join Anaconda Enterprise will be sent to the email address specified.
 - Use the **Credentials** tab to manage the user's password. If the **Temporary** switch is on, this new password can only be used once—the user will be asked to change their password after they use it to log in to Anaconda Enterprise.
 - Use the **Role Mappings** tab to assign the user one or more roles, and the **Groups** tab to add them to one or more groups. See *managing roles and groups* for more information.

Note: To grant **Authentication Center Administrators** sufficient authority to manage AE users, you'll need to assign them the `admin` role.



- Use the **Sessions** tab to view a summary of all sessions the user has started, and log them out of all sessions in a single click. This is handy if a user goes on vacation without logging out of their sessions. You can use the Operations Center to view a summary of all sessions running on specific nodes or by specific users. See [monitoring sessions and deployments](#) for more information.

To view and edit a set of fine grain permissions that you can enable and use to define policies for allowing other users to manage users in the selected realm, return to the Users list and select the **Permissions** tab:



Enabling user registration


You can use the Authentication Center to enable users to self register and create their own account. When enabled, the login page will have a **Register** link users can click to open the registration page where they can enter the user profile information and password required to create their new account.

1. Click **Realm Settings** under Configure in the menu on the left menu.
2. Click the **Login** tab, and enable the **User registration** switch.

You can change the look and feel of the registration form as well as removing or adding additional fields that must be entered. See the [Server Developer Guide](#) for more information.

Enabling required actions

You can use the **Required User Actions** drop-down list—on the **Details** tab for each user—to select the tasks that a user must complete (after providing their credentials) before they are allowed to log in to Anaconda Enterprise:



Update Profile This requires the user to update their profile information, such as their name, address, email, and phone number.


Update Password When set, a user must change their password.

Configure OTP When set, a user must configure a one-time password generator on their mobile device using either the Free OTP or Google Authenticator application.

Setting default required actions

You can specify default required actions that will be added to all new user accounts. Select **Authentication** from the Configure menu on the left and use the **Required Actions** tab to specify whether you want each required action to be enabled—available for selection—or also pre-populated as a default for all new users.

Note: A required action must be enabled to be specified as a default.



Using terms and conditions

Many organizations have a requirement that when a new user logs in for the first time, they need to agree to the terms and conditions of the website. This functionality can be implemented as a required action, but it requires some


configuration. In addition to enabling **Terms and Conditions** as a required action, you must also edit the `terms.ftl` file in the *base* login theme. See the [Server Developer Guide](#) for more information on extending and creating themes.

Impersonating users

It is often useful for an Administrator to impersonate a user. For example, a user may be experiencing an issue using an application and an Admin may want to impersonate the user to see if they can duplicate the problem.

Note: Any user with the realm's `impersonation` role can impersonate a user.

The **Impersonate** command is available from both the Users list and the **Details** tab for a user.



ID	Username	Email	Last Name	First Name	Actions
9a2c3e3-444-4954-8...	admin	admin@anaconda...	DeVries	Admin	Edit Impersonate Delete
532956a-02f4-422f-8...	anaconda-enterprise	anaconda-enterpri...	Enterprise	Anaconda	Edit Impersonate Delete
0a26c777-6878-4553-...	gus	gus@anaconda.com			Edit Impersonate Delete
200a82b6-6715-46c8-...	bednar	bednar@anaconda.c...	Bednar	James	Edit Impersonate Delete
5a2f3ab5-5f8a-4f46-...	jstevens	jstevens@anaconda.c...	Stevens	John-Luc	Edit Impersonate Delete
23675211-6a27-445b-...	marta	marta@anaconda.com	Sells	Marta	Edit Impersonate Delete
63b1a8d2-5c4d-4b41-...	user01	user01@example.com	User	User01	Edit Impersonate Delete
fbdbaa38-45d8-42ae-...	user02	user02@example.com	User	User02	Edit Impersonate Delete
ac33969-8295-4496-...	user03	user03@example.com	User	User03	Edit Impersonate Delete
7d3c9ac-9d33-4279-5...	user04	user04@example.com	User	User04	Edit Impersonate Delete
63b0b6c-9c0e-4469-...	user05	user05@example.com	User	User05	Edit Impersonate Delete
56c0566-823c-4683-...	user06	user06@example.com	User	User06	Edit Impersonate Delete
5533452-2659-4492-...	user07	user07@example.com	User	User07	Edit Impersonate Delete
6d3a27ab-8675-403b-...	user08	user08@example.com	User	User08	Edit Impersonate Delete
7f6a4af-0a34-452b-8...	user09	user09@example.com	User	User09	Edit Impersonate Delete
585c2d57-8a2f-4a2b-...	user10	user10@example.com	User	User10	Edit Impersonate Delete
3a48a716-7a47-4808-...	user11	user11@example.com	User	User11	Edit Impersonate Delete
7b0f0a0b-408a-4f8a-...	user12	user12@example.com	User	User12	Edit Impersonate Delete
13a534d-11d5-41a5-...	user13	user13@example.com	User	User13	Edit Impersonate Delete

Click **Impersonate** to display a list of applications the user has accessed on the platform, including editor sessions and deployments.

Click the `Anaconda Platform` link to interact with Anaconda Enterprise as the impersonated user.

Application	Available Permissions	Granted Permissions	Granted Personal Info	Additional Grants	Action
session_client_5d791d38b71457a4b98b751f09c7c2	Offline access	Full Access	Full Access		
my client	Offline access	Full Access	Full Access		
session_client_4b278c7879741f68808c940c650544a	Offline access	Full Access	Full Access		
session_client_a93d4d92280549235a265176c2b3001c	Offline access	Full Access	Full Access		
session_client_f57880c522454050578c2570d833066	Offline access	Full Access	Full Access		
session_client_256f051eac0d48833dc1e876421f88a	Offline access	Full Access	Full Access		
session_client_88b42134802401784f0d656c1b70f04	Offline access	Full Access	Full Access		
anaconda-deploy-proxy	Offline access, Anaconda Enterprise project deployer, Obtain permissions, Anaconda Enterprise package uploader	Full Access	Full Access		

	profile in Account				
Anaconda Platform	Offline access, Anaconda Enterprise project deployer, Obtain permissions, Anaconda Enterprise package uploader, Anaconda Enterprise project creator, Manage account in Account, View profile in Account	Full Access	Full Access	Offline Token	Revoke Grant
session_client_68b7eda764c1465bb6dca2c72564160c	Offline access	Full Access	Full Access		
session_client_a1d00839825b44e592a2b3351841f00e	Offline access	Full Access	Full Access		
session_client_a5b7e3185bd3417fa8d15fdddb555760	Offline access	Full Access	Full Access		
Anaconda Enterprise Notebooks	Offline access, Anaconda Enterprise project deployer, Obtain	Full Access	Full Access		

Note: If the Admin and the user are in the same realm, the Admin will be logged out and automatically logged in as the user being impersonated. If the Admin and user are not in the same realm, the Admin will remain logged in and be logged in as the user in that user's realm.

2.2.3 Managing roles and groups

Assigning access and permissions to individual users can be too fine-grained and cumbersome for organizations to manage, so Anaconda Enterprise enables you to assign access permissions to specific *roles*, then use *groups* to assign one or more roles to sets of users. Users inherit the attributes and role mappings assigned to each group they are members of—whether multiple or none.


The use of groups to assign permissions is entirely optional, so you can rely solely on roles to assign users permission to perform certain actions in Anaconda Enterprise.

- You'll use the Admin Console's Authentication Center to *create and manage roles and groups*. This includes creating new roles and groups, configuring defaults for each, and assigning roles to groups.
- You'll use the Admin Console's Operations Center to *configure permissions for any roles you create*, and optionally the default system roles provided by Anaconda Enterprise.

Note: When *naming* users and groups that you create, consider that Anaconda Enterprise users can add collaborators

by user or group name when *sharing their projects* and *deployments*, as well as *packages and channels*.

To access the Authentication Center:

1. Login to Anaconda Enterprise, click the **Menu** icon  in the top right corner, then click the **Administrative Console** link in the bottom of the slideout menu.
2. Click **Manage Users**.
3. Login to the Authentication Center using the Administrator credentials *configured after installation*.


To manage roles:

Use roles to authorize individual or groups of users to perform specific actions within Anaconda Enterprise. Default roles allow you to automatically assign user role mappings when any user is newly created or imported (for example, through *LDAP*).

You'll use the Authentication Center to configure new roles and specify default roles to be automatically added to all new user accounts.

1. In the Configure menu on the left, click **Roles** to display a list of roles configured for use with Anaconda Enterprise.

To get you started, Anaconda Enterprise provides a set of “realm” roles. You can use these system roles as is, or as a basis for creating your own.



Roles	
Realm Roles	
Default Roles	
Role Name	Composite
ae-admin	False
ae-creator	False
ae-deployer	False
ae-uploader	False
offline_access	False
offline_authentication	False

ae-admin Allows a user to access the Administrative console.

ae-creator Allows a user to *create new projects*.

ae-deployer Allows a user to *create new deployments from projects*.

ae-uploader Allows a user to *upload packages*.

Note: To define roles that are *global* to Anaconda Enterprise, use the realm selector in the upper left corner to switch to the **Master** realm before proceeding.


2. To create a new role, click **Add Role** on the **Realm Roles** tab.
3. Enter a name and description of the role, and click **Save**.

Note: Roles can be assigned to users automatically or require an explicit request. If a user has to explicitly request a realm role, enable the **Scope Param Required** switch. The role must then be specified using the `scope` parameter when requesting a token.

The new role is now available to be used as a default role, or *to be assigned to groups of users*.

4. To configure default roles, click the **Default Roles** tab.
 - When working with the **AnacondaPlatform** realm, you can configure default roles *for Anaconda Enterprise users* using the list of available and default **Realm Roles**.
 - When working with the **Master** realm, you can configure default roles *for a specific client or service namespace* using the list of available and default roles for the client you select from the **Client Roles** drop-down list.

Note: To customize the list of roles available for Anaconda Enterprise Admins to use, select **AnacondaPlatform-realm** from the list.




To manage groups:

1. In the Manage menu on the left, click **Groups** to display a list of groups configured for use with Anaconda Enterprise.


To get you started, Anaconda Enterprise provides a set of default groups, with different role mappings for each. You can use these defaults as is, or as a basis for creating your own. Default groups allow you to automatically assign group membership whenever a new user is created or imported.

User Groups




2. Double-click the name of a group to view information about the group and modify it:


- Use the **Role Mappings** tab to assign roles to the group from the list of available **Realm Roles** and **Client Roles**. See *managing roles* for information on how to create new roles. Permission to perform certain actions in Anaconda Enterprise are based on a user's *role*, so you can grant permissions to a group of users by mapping the associated role(s) with the group. See the section below for the steps to *configure permissions by role*.
- Use the **Members** tab to view all users who currently belong to the group. You add users to groups *at the user level* using the **Groups** tab *for the user*. See *managing users* for more information.
- Use the **Permissions** tab to enable a set of fine grain permissions to use to *define policies* for allowing Admin users to manage the group. See the section below to understand how to *configure permissions by role*.



To configure permissions for roles:

1. Log in to Anaconda Enterprise, select the **Menu** icon  in the top right corner and click the **Administrative Console** link displayed at the bottom of the slide out window.
2. Click **Manage Resources**.
3. Log in to the Operations Center using the Administrator credentials *configured after installation*.
4. Select **Configuration** from the menu on the left to display the config map for Anaconda Enterprise.

Note: If `anaconda-platform.yml` is not displayed, be sure `anaconda-enterprise-anaconda-platform.yml` is selected in the **Config maps** drop-down list.




The following sections of the config map have permissions associated with them:

- **deploy:deployers**—used to configure which users can deploy projects
- **workspace:users**—used to configure which users can open project sessions
- **storage:creators**—used to configure which users can create projects
- **repository:uploaders**—used to configure which users can upload packages to the AE repository

5. **Save a copy of this file before making any changes** to `anaconda-platform.yml`. Any changes you make to the platform configuration will impact how Anaconda Enterprise functions, so you'll want to have a backup if the need to restore a previous configuration arises.
6. Add each new role you create to the appropriate section—based on the permission you want to grant the role—and click **Apply** to save your changes.

For example, if you create a new role called `ae-managers`, and you want users with this role to be able to deploy applications, you need to add that role to the list of roles under `deploy:deployers` to map the permission to the role.



2.2.4 Managing System Administrators


Anaconda Enterprise distinguishes between System Administrators responsible for authorizing AE platform *users*, and System Administrators responsible for managing AE *resources*. This enables enterprises to grant the permissions


required for configuring each to different individuals, based on their area of responsibility within the organization.

- Sys Admins who are granted permission to access the **Authentication Center** can *configure authentication for all platform users*, including platform Admins. See managing users for information on how to create and manage Authentication Center Admins.
- Sys Admins who are granted permission to access the **Operations Center** can *manage AE resources* and *configure advanced platform settings*.

Note: The login credentials for the Operations Center are initially set as part of the post-install configuration process. Follow the steps outlined below to authorize additional Admin users to manage cluster resources, *using the Operations Center UI* or *using a command line*. If you prefer to use OpenID Connect (OIDC), see [oidc](#).

Managing Operations Center Admins using the UI

1. Log in to Anaconda Enterprise, select the **Menu** icon  in the top right corner and click the **Administrative Console** link displayed at the bottom of the slide out window.
2. Click **Manage Resources**.
3. Login to the Operations Center using the Administrator credentials configured after installation.
4. Select **Settings** in the login menu in the upper-right corner.



5. In the left menu, select **Users**, then click **+ New User** in the upper-right corner.
6. Select @teleadmin from the **Roles** drop-down list, and click **Create invite link**.

New User

Name:


Roles:

Every user must be given at least one role, otherwise he will not be able to login

[Create invite link](#) [Cancel](#)


- Copy the invitation URL that is generated, replace the private IP address with the fully-qualified domain name of the host, if necessary, and send it to the individual using your preferred method of secure communication. They'll use it to set their password, and will be automatically logged in to the Operations Center when they click **Continue**.

To generate a new invitation URL, select **Renew invitation** in the **Actions** menu for the user.



Select **Revoke invitation** to prevent them from being able to use the invitation to create a password and access the Operations Center. This effectively deletes the user before they have a chance to set their credentials.

To delete—or otherwise manage—an Operations Center user after they have set their credentials and completed the authorization process, select the appropriate option from the **Actions** menu.



Managing Operations Center Admins using a command line

To create a new Admin:

Run the following commands *on the Anaconda Enterprise master node*, replacing `<email>` and `<yourpass>` with the email address and password for the user:

```
sudo gravity enter
gravity --insecure user create --type=admin --email=<email> --password=<yourpass> --
  ↳ops-url=https://gravity-site.kube-system.svc.cluster.local:3009
```

To verify that the user was created, run the following command:

```
sudo gravity resource get users
```

To update an Admin user's password:

To update an Admin user's password, you'll need to delete the user account, then re-create it, replacing `<email>` and `<yourpass>` with the email address and new password:

```


sudo gravity enter
gravity --insecure user delete --email=<email> --ops-url=https://gravity-site.kube-
↪system.svc.cluster.local:3009
gravity --insecure user create --type=admin --email=<email> --password=<yourpass> --
↪ops-url=https://gravity-site.kube-system.svc.cluster.local:3009


```

2.2.5 Configuring session timeouts

As an Administrator, you can configure session timeouts for Anaconda Enterprise platform users, to help you adhere to your organization's security standards or enforce policies.

You'll use the Administrative Console's Authentication Center to set the various parameters related to session timeouts:

1. Login to Anaconda Enterprise, click the **Menu** icon  in the top right corner, then click the **Administrative Console** link in the bottom of the slideout menu.
2. Click **Manage Users**.
3. Login to the Authentication Center using the Administrator credentials required to be able to access it.
4. In the Configure menu on the left, select **Realm Setting**.
5. Click the **Tokens** tab at the top to display the following:



The screenshot shows the AnacondaPlatform Administrative Console. The left sidebar is expanded, showing the 'Configure' menu with 'Realm Settings' selected. The main content area is titled 'AnacondaPlatform' and shows the 'Tokens' tab selected. The 'Tokens' tab contains several configuration options for session timeouts, each with a numeric input field and a unit dropdown menu.

Configuration Option	Value	Unit
Revoke Refresh Token	OFF	-
SSO Session Idle	1	Hours
SSO Session Max	1	Days
Offline Session Idle	30	Days
Access Token Lifespan	1	Hours
Access Token Lifespan For Implicit Flow	1	Hours
Client login timeout	1	Minutes
Login timeout	30	Minutes
Login action timeout	5	Minutes
User-initiated Action Lifespan	5	Minutes
Default Admin-initiated Action Lifespan	12	Hours
Override User-initiated Action Lifespan	Select one...	Minutes

6. Use the available configuration options to specify maximum thresholds for each aspect of user sessions, including the following:
 - Time limits for idle browser sessions and single sign on (SSO) tokens
 - Lifespans for OpenID access tokens
 - Time limits for login-related actions, such as resetting a forgotten password

Configuration option	Description
Revoke Refresh Token	If enabled, limits refresh tokens to one-time use
SSO Session Idle	User will be logged out of session if inactive for this length of time
SSO Session Max	Maximum time a user session can remain active, regardless of activity
Offline Session Idle	Amount of time an offline session can be idle before the access token is revoked
Access Token Lifespan	Amount of time an access token will remain valid, before expiring
Access Token Lifespan For Implicit Flow	Timeout for access tokens created with Implicit Flow—no refresh token is provided
Client login timeout	Maximum time a client can take to complete the authorization process
Login timeout	Maximum time a user can take to authenticate before the process restarts
Login action timeout	Maximum time a user can spend on any one page in the authentication process
User-Initiated Action Lifespan	Maximum time before a user-initiated action (e.g., forgot password email) expires
Default Admin-Initiated Action Lifespan	Maximum time before an admin-initiated action (e.g., issue token to user) expires
Override User-Initiated Action Lifespan	Use to optionally configure different timeouts for each user-initiated action

7. Click **Save** to save your changes to the Anaconda Enterprise platform.

2.2.6 LDAP setup example

Configuring identity and access management is complex, and each enterprise has a different LDAP directory structure. While your implementation will be based on the specific structure and needs of your organization, the principles and processes outlined here will enable you to:

- **Reduce the number of users** that need to be mapped into Anaconda Enterprise (by mapping a functional role—AE5 User—to an LDAP group). This also simplifies licence management through a single group membership.
- **Reduce the number of groups** that are mapped into Anaconda Enterprise (by filtering groups to include only relevant functional roles and team memberships).
- **Automate the import of new groups** for team memberships based on filters.
- **Automate the provision of AE5 roles to users** based on group membership of functional roles.

Roles are used to determine the types of objects in Anaconda Enterprise that users with the role can access using the platform, such as *packages* or *projects*. This example is provided to help guide you through the process of mapping default Anaconda Enterprise roles to the following common functional business roles:

- Business Analyst
- Data Scientist
- Data Engineer
- DevOps
- Administrator

Follow the general processes outlined below for your specific implementation:

1. *Retrieving directory structures and user attributes*
2. *Setting up user federation*


3. *Testing your identity provider setup*
 4. *Configuring group mappers*
 5. *Mapping group roles*
-

Retrieving directory structures and user attributes

The organizational structure of your enterprise is represented in LDAP by a directory structure or tree. You'll need to request the bind user credentials from your Security Administrator.

While you can make assumptions about the directory structure based on the bind user credentials, it's extremely difficult to setup an identity provider without the complete structure. For example, if the bind user credentials are `uid=binduser,cn=users,cn=accounts,dc=tools,dc=continuum,dc=io`, we can deduce that the root or base of the tree is `dc=tools,dc=continuum,dc=io`.

Tools are available to help you visualize your organization's directory structure. For example, `phpldapadmin` generated the following view:



The rest of the bind user credentials become apparent after looking at the directory structure. In this example, we can see that *users* live under `cn=accounts > cn=users`, and *groups* live under `cn=accounts > cn=groups`.

Now that you know the directory structure, you can gather information about the user and group entries that you'll need later.

You can use the `ldapsearch` tool—along with the `binduser` credentials—to learn details about an individual user based on their uid. Here's a sample command for the user `gandalf`:

```
ldapsearch -D 'uid=binduser,cn=users,cn=accounts,dc=tools,dc=continuum,dc=io' -W -H_
↪ ldap://ipa.tools.continuum.io -b dc=tools,dc=continuum,dc=io "(uid=gandalf)"
```

Results will resemble the following:

```
# gandalf, users, compat, tools.continuum.io
dn: uid=gandalf,cn=users,cn=compat,dc=tools,dc=continuum,dc=io
objectClass: posixAccount
objectClass: ipaOverrideTarget
objectClass: top
gecos: gandalf the grey
cn: gandalf the grey
uidNumber: 1666600031
gidNumber: 1666600031
```

(continues on next page)

(continued from previous page)

```

loginShell: /bin/sh
homeDirectory: /home/gandalf
ipaAnchorUUID:: OklQQTp0b29scy5jb250aW51dW0uaW86OTEyYTMwNjgtZDhmYy0xMWU4LTgzYT
UtMTIyYTE3YWNIzJh
uid: gandalf

# gandalf, users, accounts, tools.continuum.io
dn: uid=gandalf,cn=users,cn=accounts,dc=tools,dc=continuum,dc=io
displayName: gandalf the grey
uid: gandalf
krbCanonicalName: gandalf@TOOLS.CONTINUUM.IO
objectClass: top
objectClass: person
objectClass: organizationalperson
objectClass: inetorgperson
objectClass: inetuser
objectClass: posixaccount
objectClass: krbprincipaux
objectClass: krbticketpolicyaux
objectClass: ipaobject
objectClass: ipasshuser
objectClass: ipaSshGroupOfPubKeys
objectClass: mepOriginEntry
loginShell: /bin/sh
initials: gt
gecos: gandalf the grey
sn: the grey
homeDirectory: /home/gandalf
mail: gandalf@tools.continuum.io
krbPrincipalName: gandalf@TOOLS.CONTINUUM.IO
givenName: gandalf
cn: gandalf the grey
ipaUniqueID: 912a3068-d8fc-11e8-83a5-122a17ace32a
uidNumber: 1666600031
gidNumber: 1666600031
krbPasswordExpiration: 20181026085310Z
krbLastPwdChange: 20181026085310Z
memberOf: cn=ipausers,cn=groups,cn=accounts,dc=tools,dc=continuum,dc=io
memberOf: cn=grp-ae5-user,cn=groups,cn=accounts,dc=tools,dc=continuum,dc=io
memberOf: cn=grp-ae5-wizards,cn=groups,cn=accounts,dc=tools,dc=continuum,dc=io
memberOf: cn=grp-lord-of-the-rings,cn=groups,cn=accounts,dc=tools,dc=continuum
,dc=io

# search result
search: 2
result: 0 Success


# numResponses: 3
# numEntries: 2


```

Within these results, you'll find the information you need to *set up user federation for LDAP*.

Setting up LDAP user federation

You'll use the Anaconda Enterprise Administrative Console's Authentication Center to add LDAP as your identity provider:

1. Login to Anaconda Enterprise, click the **Menu** icon  in the top right corner, then click the **Administrative Console** link in the bottom of the slideout menu.
2. Click **Manage Users** and login to the Authentication Center using the Administrator credentials *configured after installation*.



3. In the Configure menu on the left, select **User Federation**.
4. Select `ldap` from the Add provider selector to display the Add user federation provider **Required Settings**.
5. Configure the fields as follows: (**Bold** items are described in more detail below the table.)

Field	Setting
Enabled	ON
Console Display Name	ldap(tools.continuum.io)
Priority	0
Import Users	ON
Edit Mode	READ_ONLY
Sync Registration	OFF
Vendor	Red Hat Directory Server
Username LDAP attribute	uid
RDN LDAP attribute	uid
UUID LDAP attribute	uidNumber
User Object Classes	person,organizationalperson,inetorgperson
Connection URL	ldap://ipa.tools.continuum.io:389
Users DN	cn=users,cn=accounts,dc=tools,dc=continuum,dc=io
Authentication Type	simple
Bind DN	uid=binduser,cn=users,cn=accounts,dc=tools,dc=continuum,dc=io
Bind Credential	
Custom User LDAP Filter	(&(objectClass=person)(uid=*)(memberOf=cn=grp-ae5-user,cn=groups,cn=accounts,dc=tools,dc=continuum,dc=io))
Search Scope	One level
Validate Password Policy	OFF
User Truststore SPI	Only for ldaps

Table 1 – continued from previous page

Field	Setting
Connection Pooling	ON
Connection Timeout	
Read Timeout	
Pagination	ON
Allow Kerberos authentication	OFF
User Kerberos for Password Authentication	OFF
Batch Size	1000
Periodic Full Sync	OFF
Periodic Changed Users Sync	OFF
Cache Policy	DEFAULT

Vendor

When you select a vendor from the drop-down list, default values for the the most commonly used attributes will be prefilled. Be sure to select the correct one, and **note that the default values may not match the way your organization has set up their application**. Our example uses Red Hat Directory Server, which is based on Free IPA.

Username, RDN, UUID, User Object Classes, Users DN and Bind DN

Locate the values for these fields in the results of the `ldapsearch` command you ran previously. The following table outlines how the fields map to the relevant values from our `gandalf` user example:

Field	LDAP Search Value	Description
Username	uid: gandalf	The unique ID used to identify the user.
RDN	uid: gandalf	Usually the same as the Username, but may default to something else depending on the vendor selected
UUID	uidNumber: 1666600031	Unique identifier
User Object Classes	objectClass: person objectClass: organizationalperson objectClass: inetorgperson	User object classes combined in a single field
Users DN	dn: uid=gandalf,cn=users,cn=accounts,dc=tools,dc=continuum,dc=io	The dn for the user entry
Bind DN	uid=binduser,cn=users,cn=accounts,dc=tools,dc=continuum,dc=io	Usually provided by Security Admin

Custom User LDAP Filter

You can use a custom filter to restrict which users are returned from LDAP. In this case, we want only those persons (`objectClass=person`) with any uid (`uid=*`) that are a member of group `grp-ae5-user` (`memberOf=cn=grp-ae5-user,cn=groups,cn=accounts,dc=tools,dc=continuum,dc=io`). No other users will be able to log in, thereby preventing unauthorized access. This is also useful for managing licences, as users will have to be explicitly added to this group to be able to access the platform.

Filters also limit the need to synchronize a large number of objects from LDAP, which will help prevent out of memory errors in the `auth pod`.


Note: Avoid the temptation to add new groups into the Custom User LDAP Filter. LDAP search criteria are notorious for their complexity, and if it's implemented incorrectly, all user access could be suspended or functionality disabled.

Testing your provider setup

Use the **Test connection** and **Test authentication** buttons to verify that the platform can connect to the provider with the credentials provided. You'll need to resolve any errors before continuing.

By default, users will not be synced from LDAP until they log in. To test whether the **Custom User LDAP Filter** is working correctly, you can add or remove users in LDAP, then enable the sync settings to see if your changes are picked up and user authentication works as expected.

After you save the **Required Settings**, the provider is listed under **User Federation**:



Configuring group mappers

After you have successfully set up user federation, set up a group mapper for your identify provider using the **Mappers** tab. For example, you can create one called `ldap-group-mapper` and configure it based on the results generated by the `ldapsearch` command. In this case, we ran the command against a known group to retrieve additional information needed:

```
ldapsearch -D 'uid=binduser,cn=users,cn=accounts,dc=tools,dc=continuum,dc=io' -W -H_
↪ ldap://ipa.tools.continuum.io -b dc=tools,dc=continuum,dc=io "(cn=grp-ae5-user)"
```

With the following results:

```
# grp-ae5-user, groups, compat, tools.continuum.io
dn: cn=grp-ae5-user,cn=groups,cn=compat,dc=tools,dc=continuum,dc=io
objectClass: posixGroup
objectClass: ipaOverrideTarget
objectClass: ipaexternalgroup
objectClass: top
gidNumber: 1666600026
memberUid: czhang
memberUid: dlawrence
memberUid: edill
memberUid: escissorhands
memberUid: gcavanaugh
memberUid: jsandhu
memberUid: rbarthelmie
memberUid: vghadban
memberUid: gandalf
ipaAnchorUUID:: OklQQTP0b29scy5jb250aW51dW0uaW86NGFhOTQ4NzYtZDg4YS0xMWU4LWE2ZD
ctMTIyYTE3YWNIzMzJh
cn: grp-ae5-user

# grp-ae5-user, groups, accounts, tools.continuum.io
dn: cn=grp-ae5-user,cn=groups,cn=accounts,dc=tools,dc=continuum,dc=io
objectClass: top
objectClass: groupofnames
objectClass: nestedgroup
```

(continues on next page)

(continued from previous page)

```

objectClass: ipausergroup
objectClass: ipaobject
objectClass: posixgroup
cn: grp-ae5-user
ipaUniqueID: 4aa94876-d88a-11e8-a6d7-122a17ace32a
gidNumber: 1666600026
member: uid=czhang,cn=users,cn=accounts,dc=tools,dc=continuum,dc=io
member: uid=dlawrence,cn=users,cn=accounts,dc=tools,dc=continuum,dc=io
member: uid=edill,cn=users,cn=accounts,dc=tools,dc=continuum,dc=io
member: uid=escissorhands,cn=users,cn=accounts,dc=tools,dc=continuum,dc=io
member: uid=gcavanaugh,cn=users,cn=accounts,dc=tools,dc=continuum,dc=io
member: uid=jsandhu,cn=users,cn=accounts,dc=tools,dc=continuum,dc=io
member: uid=rbarthelmie,cn=users,cn=accounts,dc=tools,dc=continuum,dc=io
member: uid=vghadban,cn=users,cn=accounts,dc=tools,dc=continuum,dc=io
member: uid=gandalf,cn=users,cn=accounts,dc=tools,dc=continuum,dc=io

# search result
search: 2
result: 0 Success

# numResponses: 3
# numEntries: 2

```

Field	LDAP Search Value
Name *	ldap-group-mapper
Mapper Type	group-ldap-mapper
LDAP Groups DN	cn=groups,cn=accounts,dc=tools,dc=continuum,dc=io
Group Name LDAP Attribute	cn
Group Object Classes	groupOfNames
Preserve Group Inheritance	ON
Ignore Missing Groups	OFF
Membership LDAP Attribute	member
Membership Attribute Type	DN
Membership User LDAP Attribute	uid
LDAP Filter	(cn=grp-ae5*)
Mode	READ_ONLY
User Groups Retrieve Strategy	LOAD_GROUPS_BY_MEMBER_ATTRIBUTE
Member-Of LDAP Attribute	memberOf
Mapped Group Attributes	
Drop non-existing groups during sync	OFF

Note: Avoid the temptation to add new groups into the LDAP Filter in the Group Mapper. LDAP search criteria are notorious for their complexity, and if it's implemented incorrectly all user access could be suspended or functionality disabled.

LDAP Groups DN

Derived from the `ldapssearch` field: `dn: cn=grp-ae5-user,**cn=groups,cn=accounts,dc=tools,dc=continuum,dc=io**`

Group Name LDAP Attribute

Derived from the `ldapssearch` field: `cn: grp-ae5-user`

Group Object Classes

A default should have been selected. In this case it is `objectClass: groupofnames`.

LDAP Filter

All relevant groups—whether they are based on functional role or team membership—have been set up with the prefix `grp-ae5-`. This prefix is used to filter the relevant groups from the User Federation provider, preventing any unnecessary groups from being pulled into the AE platform.

For example, the user Gandalf is a member of the following groups:

```
memberOf: cn=ipausers,cn=groups,cn=accounts,dc=tools,dc=continuum,dc=io
memberOf: cn=grp-ae5-user,cn=groups,cn=accounts,dc=tools,dc=continuum,dc=io
memberOf: cn=grp-ae5-wizards,cn=groups,cn=accounts,dc=tools,dc=continuum,dc=io
memberOf: cn=grp-lord-of-the-rings,cn=groups,cn=accounts,dc=tools,dc=continuum
```

If you perform a group synchronisation, only the groups in **bold** will be imported. Additionally, when Gandalf logs in, only the `grp-ae5-`-prefixed groups from his profile will be imported. You can test this by deleting the `grp-ae5-wizards` group, then login as the user `gandalf`. His team membership group `grp-ae5-wizards` will be visible in the Auth Center, but the group `grp-lord-of-the-rings` will be filtered out and therefore not imported.

Mapping group roles

As a final step, you can map Anaconda Enterprise roles to the LDAP groups that are imported into the platform.

In this example, we'll assign functional role groups the default roles that will allow them to interact with the platform in a way that makes sense for the business. You can also *create custom roles*, if needed.

LDAP Group	ae-admin	ae-creator	ae-deployer	ae-uploader	of-line	uma_authentication	Description
grp-ae5-biz-analyst					X		Business Analysts can access the system. They cannot create projects or grant others access to the system.
grp-ae5-data-scientist		X	X	X	X	X	Data Scientists can create and share projects, but cannot deploy them.
grp-ae5-data-engineer		X		X	X	X	Data Engineers can additionally deploy projects, as well as grant access to others.
grp-ae5-devops			X	X	X		DevOps can deploy projects and upload packages, but cannot create projects.
grp-ae5-sec-admin							This group should be used to administer user access within the system. Therefore, no roles should be defined in the AnacondaPlatform realm. If required, roles can be defined and access granted in the Auth Center Master realm.
grp-ae5-sysadmin	X						By default, the ae-admin role is a superuser for all other roles.
grp-ae5-sysacct							The roles for system accounts are yet to be defined. These could be used for automated CI/CD tasks.
grp-ae5-user							This is used as a coarse-grained control for access to AE5, so no roles are defined.
grp-ae5-wizards							This is a team membership role, so no AE roles are defined for it.

Note: Functional role groups should be setup once and left alone.


Use the **Role Mappings** tab to assign the appropriate role(s) to each group:

2.2.7 Google IAM setup example

In addition to providing out-of-the-box support for LDAP, Active Directory, SAML and Kerberos, Anaconda Enterprise also enables you to configure the platform to use other external identity providers to authenticate users. If your enterprise uses Google's Cloud IAM (Identity and Access Management) to manage access to Google Cloud Platform (GCP) resources, for example, you can use the following process to configure the platform to use Cloud IAM as your identity provider. This will allow users to log in to the platform using their Google (or G-Suite) credentials.

Before you begin:

- You'll need to configure a [Google Cloud project](#) on GCP.
- You'll need to *enable the Google+ API* for the project.




- You'll need to *create the credentials* to use to authorize the platform to connect to Google IAM.

Enabling the Google+ API


With your project selected in *Google Cloud Platform*:

1. Select **APIs & Services** from the menu on the left.
2. Select **ENABLE APIs AND SERVICES**, then locate and select the Google+ API card in the API library.



3. Click **ENABLE**.

Now you can create credentials for the platform to access your Google Cloud project.




Creating Google+ credentials

With your project selected in *Google Cloud Platform*:

1. Select **APIs & Services > Credentials** from the menu on the left.
2. Click **Create credentials** and select **Help me choose** from the drop-down menu.

Note: If you haven't already, be sure to *enable the Google+ API* before proceeding.



3. Select **Google+ API** from the API drop-down list, **Web server** from the next drop-down, and **User data** for the last question.
4. Click **What credentials do I need?** to create the appropriate credentials for the platform.

Credentials

Add credentials to your project

1 Find out what kind of credentials you need

We'll help you set up the correct credentials

If you wish you can skip this step and create an [API key](#), [client ID](#), or [service account](#)

Which API are you using?

Different APIs use different auth platforms and some credentials can be restricted to only call certain APIs.

Google+ API

Where will you be calling the API from?

Credentials can be restricted using details of the context from which they're called. Some credentials are unsafe to use in certain contexts.

Web server (e.g. node.js, Tomcat)

What data will you be accessing?

Different credentials are required to authorize access depending on the type of data that you request.

☒ **User data**

Access data belonging to a Google user, with their permission

☐ **Application data**

Access data belonging to your own application

What credentials do I need?

2 Get your credentials

Cancel

Credentials

Add credentials to your project

☒ Find out what kind of credentials you need

Calling Google+ API from a web server

2 Create an OAuth 2.0 client ID

Name ⓘ

Web client 1

Restrictions

Enter JavaScript origins, redirect URIs, or both [Learn More](#)

Origins and redirect domains must be added to the list of Authorized Domains in the [OAuth consent settings](#).

Authorized JavaScript origins

For use with requests from a browser. This is the origin URI of the client application. It can't contain a wildcard ([https://*.example.com](#)) or a path ([https://example.com/subdir](#)). If you're using a nonstandard port, you must include it in the origin URI.

<https://www.example.com>

Authorized redirect URIs

For use with requests from a web server. This is the path in your application that users are redirected to after they have authenticated with Google. The path will be appended with the authorization code for access. Must have a protocol. Cannot contain URL fragments or relative paths. Cannot be a public IP address.

<https://www.example.com>

Create OAuth client ID


5. Enter a meaningful name, such as `Anaconda Enterprise`, to identify the platform (and help differentiate it from any other web applications you may have configured to use Google IAM).
6. In the **Authorized JavaScript origins** field, provide the FQDN of the Anaconda Enterprise server instance.
7. *Open the Anaconda Enterprise Auth Center (see instructions below), and copy and paste the value from the **Redirect URI** field into the **Authorized redirect URIs** field here.*


Note: If the domain is not an authorized domain, you'll see an `Invalid Redirect` error, and be prompted to add it to the authorized domains list before proceeding.

8. Click **Create OAuth client ID**.
9. On the **OAuth consent screen** tab:
 - Set the **Application type** to **Public**.
 - Set the **Application name** to `Anaconda Enterprise` (or something else meaningful to platform users).
 - Optionally, upload a logo to help users recognize Anaconda Enterprise.
 - Provide a **Support email** address for users to reach out for help.
 - Provide the full path to the authorized homepage where users will access Anaconda Enterprise.
 - Optionally provide authorized links to a your organization's privacy policy and terms of service.
9. Click **Create** to display the OAuth client credentials that you'll need to copy and paste into Anaconda Enterprise, to enable the platform to authenticate with Google. (See Step 5 below.)

Configuring Google to be your identity provider

Now that you've configured your GCP project to work with Anaconda Enterprise, you need to use the Anaconda Enterprise Administrative Console's Authentication Center to configure Google as your external identity provider:

1. Login to Anaconda Enterprise, click the **Menu** icon  in the top right corner, then click the **Administrative Console** link in the bottom of the slideout menu.
2. Click **Manage Users** and login to the Authentication Center using the Administrator credentials *configured after installation*.



3. In the Configure menu on the left, select **Identity Providers** and select Google from the Add provider drop-down list.
4. The **Settings** tab displays the **Redirect URI** you need to copy to the Google Cloud project's configuration. The Redirect URI will look similar to this: `https://<full-qualified-domain-name>/auth/realms/AnacondaPlatform/broker/google/endpoint`.
5. Copy and paste the credentials from GCP (Step 9 above) into the **Client ID** and **Client Secret** fields, and click **Save**.

Now that you've completed the configuration, the Anaconda Enterprise login screen will include a Google login option.



Note: When users choose this option and log in to the platform, they'll be automatically added as new AE users. As an Administrator, you can then configure their group assignments and role mappings. For more information, see [Managing roles and groups](#).

2.3 Configuring channels and packages

Anaconda Enterprise enables you to distribute software through the use of *channels* and *packages*. Channels represent locations of repositories where Anaconda Enterprise looks for packages. Packages are used to bundle software files and information about the software—such as its name, specific version and description—into a single file that can be easily installed and managed.

NOTE: Anaconda Enterprise supports the use of both conda and pip packages in its repository.

The process for distributing packages within an organization resembles the following:

1. Configure access to a cloud-based repository or a private location on a remote or local repository that you or your organization created. See [Accessing remote package repositories](#) for more information.
2. Mirror *the entire Anaconda repository* or *specific packages*. You can also mirror packages in a repository *in an airgapped environment without internet access*.
3. Share channels with specific users or groups to give them access to the packages within the channel. You can copy packages from one channel into another, customize each channel by including different versions of packages, and delete channels when they are no longer needed. See [Managing channels and packages](#) for more information.

Your organization can also optionally configure Anaconda Enterprise to [point conda to an on-premises repository](#), or [use a proxy for conda packages](#).



2.3.1 Accessing remote package repositories

As an Administrator, you can configure Anaconda Enterprise to use packages from an online package repository such as `anaconda` and `r`.

You can then *mirror channels & packages* into your organization's internal AE repository so users can access the packages from a centralized, on-premises location.

If users are permitted to install packages from off-site package repositories, you can make it easier for users to access them from within their editing sessions by configuring them as default channels.

To do so, *edit your Anaconda Enterprise configuration*—`anaconda-enterprise-anaconda-platform.yml`—to include the appropriate channels, as follows:

```
conda:
  channels:
    - defaults
  default_channels:
    - https://repo.anaconda.com/pkgs/main
    - https://repo.anaconda.com/pkgs/free
    - https://repo.anaconda.com/pkgs/r
  channel_alias: https://<ANACONDA_ENTERPRISE_FQDN>/repository/conda
```

To update Anaconda Enterprise with your changes to the configuration, restart its services:

```
sudo gravity enter
kubectl get pods | grep 'ap-' | cut -d' ' -f1 | xargs kubectl delete pods
```

2.3.2 Mirroring channels and packages

Anaconda Enterprise enables you to create a local copy of a repository so users can access the packages from a centralized, on-premises location.

The mirror can be complete, partial, or include specific packages or types of packages. You can also create a mirror in an air gapped environment to help improve performance and security.

Note: It can take hours to mirror the full repository.

Before you can use Anaconda Enterprise's convenient syncing tools to configure local mirrors for channels and packages, you'll need to *configure access to the source of the packages* to be mirrored, whether an online repository or a

tarball (if an airgapped installation).

Prerequisites:

- *Install and configure Anaconda Enterprise*
- *Install conda*
- *Install the Anaconda Enterprise CLI*

Types of mirroring:

- To create a complete mirror, see *Mirroring the Anaconda repository* or *Mirroring a PYPI repository*.
- To create partial mirror, see *Mirroring specific packages*.
- To mirror a repository in a system without internet access, see *Mirroring in an air-gapped environment*.
- To share mirrors, see *Configuring Anaconda Enterprise* and *Sharing channels*.

Configuration options:

- *Configuring SSL verification*
- *Mirroring in a proxied environment*
- *Mirroring specific platforms and versions*
- *Using blacklisting to exclude packages*
- *Using whitelisting to include packages*
- *Combining multiple configuration arguments*

Log into Anaconda Enterprise as an existing user using the following command:

```
$ anaconda-enterprise-cli login
Username: anaconda-enterprise
Password:
Logged anaconda-enterprise in!
```

Note: If Anaconda Enterprise 5 is installed in a proxied environment, see *Mirroring in a proxied environment* for information on setting the NO_PROXY variable.

Mirroring the Anaconda repository

We recommend the following process as a best practice for mirroring the Anaconda repository.

1. Instead of using the default `anaconda.yaml` file included in the mirror tool installation, create two `yaml` files, one for mirroring the `main` channel, and another for mirroring the `free` channel.

Example `main.yaml` file:

```
dest_channel: main
channels:
  - https://repo.anaconda.com/pkgs/main
platforms:
  - linux-64
  - noarch
```

Example `free.yaml` file:

```
dest_channel: free
channels:
  - https://repo.anaconda.com/pkgs/free
platforms:
  - linux-64
  - noarch
```

2. If you saved both of these files to the home directory, you can use the following commands to mirror these channels. Otherwise, amend the path so that it corresponds to where you saved the files:

```
cas-sync-api-v5 --file ~/main.yaml
cas-sync-api-v5 --file ~/free.yaml
```

This mirrors all of the packages from these channels in the Anaconda repository. If the channel doesn't already exist, it will be automatically created and shared with all authenticated users. You can customize the permissions on the mirrored packages by [sharing the channel](#).

Tip: If you plan to mirror these channels on a regular basis, consider adding the `-c` flag to get a clean mirror each time. This will automatically remove any packages that have been removed from the Anaconda repository between mirrors from your internal repository—excluding any packages your organization has blacklisted.

3. Verify that the mirror was successful by logging into your account and navigating to the **Packages** tab. You should see a list of the mirrored packages.
-

Mirroring a PyPI repository

The full PyPI mirror size is currently [close to 4TB](#), so ensure that your file storage location has sufficient disk space before proceeding. Rather than mirror the entire PyPI repository, you can use a configuration file such as `$PREFIX/etc/anaconda-platform/mirrors/pypi.yaml` to customize the mirror behavior and specify the subset of packages you want to mirror.

To create a PyPI mirror:

```
anaconda-enterprise-cli mirror pypi --config pypi.yaml
```

This command loads the packages on `https://pypi.org` into the `pypi` user account. Mirrored packages can be viewed at `<https://anaconda.example.com>/repository/pypi/pypi/simple/`, replacing `<https://anaconda.example.com>` with the actual URL to your installation of Anaconda Enterprise. (The second `pypi` in the url should match the user configuration value described below.)

The following configuration options are available for you to customize your configuration file:

Name	Description
<code>user</code>	The local user under which the PyPI packages are imported. Default: <code>pypi</code> .
<code>pkg_list</code>	A list of packages to mirror. Only packages listed are mirrored. If this is set, <code>blacklist</code> and <code>whitelist</code> settings are ignored. Default: <code>[]</code> .
<code>whitelist</code>	A list of packages to mirror. Only packages listed are mirrored. If the list is empty, all packages are checked. Default: <code>[]</code> .
<code>blacklist</code>	A list of packages to skip. The packages listed are ignored. Default: <code>[]</code> .
<code>latest_only</code>	Only download the latest versions of the packages. Default: <code>false</code> .
<code>remote_url</code>	The URL of the PyPI mirror. <code>/pypi</code> is appended to build the XML RPC API URL, <code>/simple</code> for the simple index and <code>/pypi/{package}/{version}/json</code> for the JSON API. Default: <code>https://pypi.python.org/</code> .
<code>xml_rpc_url</code>	A custom value for XML RPC URL. If this value is present, it takes precedence over the URL built using <code>remote_url</code> . Default: <code>null</code> .
<code>simple_index_url</code>	A custom value for the simple index URL. If this value is present, it takes precedence over the URL built using <code>remote_url</code> . Default: <code>null</code> .
<code>use_xml_rpc</code>	Whether to use the XML RPC API as specified by PEP381 . If this is set to <code>true</code> , the XML RPC API is used to determine which packages to check. Otherwise the scripts falls back to the simple index. If the XML RPC fails, the simple index is used. Default: <code>true</code> .
<code>use_serial</code>	Whether to use the serial number provided by the XML RPC API. Only packages updated since the last serial saved are checked. If this is set to <code>false</code> , all PyPI packages are checked for updates. Default: <code>true</code> .
<code>create_org</code>	Create the mirror user as an organization instead of a regular user account. All superusers are added to the “Owners” group of the organization. Default: <code>false</code> .

Note that all mirrored PyPI-like channels are publicly available to pull packages from both inside and outside the cluster (i.e. no auth token required).

EXAMPLE:

```
whitelist:
  - requests
  - six
  - numpy
  - simplejson
latest_only: true
remote_url: https://pypi.org/
use_xml_rpc: true
```

Configuring pip

To configure pip to use this new mirror, create `pip.conf` as follows:

```
[global]
index-url=<https://anaconda.example.com>/repository/pypi/pypi/simple/
```

replacing `<https://anaconda.example.com>` with the actual URL to your Anaconda Enterprise.

To configure Anaconda Enterprise sessions and deployments to automatically use the `pip.conf` run the following command.

```
anaconda-enterprise-cli spark-config --config /etc/pip.conf pip.conf
```

Alternately, if you can use the `--index-url` flag directly when invoking `pip`. For example,

```
pip install --index-url <https://anaconda.example.com>/repository/pypi/pypi/simple/  
↪<package_name>
```

replacing `<https://anaconda.example.com>` with the actual URL to your Anaconda Enterprise installation, and `<package_name>` with the name of a package that is in your local mirror. In the example URL, the second `pypi` should match the `user` configuration value described above.

For more specific information on configuring `pip`, refer to the official documentation at https://pip.pypa.io/en/stable/user_guide/#config-file.

Mirroring specific packages

Alternately, you may not wish to mirror all packages. In this case, you can specify which platforms or specific packages you want to mirror —or— use the `whitelist`, `blacklist` or `license_blacklist` functionality to control which packages are mirrored, by editing the provided mirror files. *You cannot combine these methods.* For more information, see [Mirror configuration options](#).

```
cas-sync-api-v5 --file ~/my-custom-anaconda.yaml
```

Mirroring R packages

An example configuration file for mirroring R packages is also provided:

```
# This is destination channel of mirrored packages on your local repository.
dest_channel: r

# conda packages from these channels are mirrored to dest_channel on your local_
↪repository.
channels:
  - https://repo.anaconda.com/pkgs/r/

# if doing a mirror from an airgap tarball, the channels should point to the tarball:
# channels:
#   - file:///path-to-expanded-tarball/repo-mirrors-<date>/r/pkgs/

# Only conda packages of these platforms are mirrored.
# Omitting this will mirror packages for all platforms available on specified_
↪channels.
# If the repository will only be used to install packages on the v5 system, it only_
↪needs linux-64 packages.
platforms:
  - linux-64
```

```
cas-sync-api-v5 --file ~/cas-mirror/etc/anaconda-platform/mirrors/r.yaml
```

Mirroring in an air-gapped environment

To mirror the repository in a system with no internet access, create a local copy of the repository using a USB drive provided by Anaconda, and point `cas-sync-api-v5` to the extracted tarball.

First, mount the USB drive and extract the tarball. In this example we will extract to `/tmp`:

```
cd /tmp
tar xvf <path to>/mirror.tar
```

Note: Replace `<path to>` with the actual path to the mirror file.

Now you have a local file-system repository located at `/tmp/mirror/pkgs`. You can mirror this repository by editing `<path to cas-mirror>/etc/anaconda-platform/mirrors/anaconda.yaml` to contain:

```
channels:
  - /tmp/mirror/pkgs
```

And then run the command:

```
cas-sync-api-v5 --file etc/anaconda-platform/mirrors/conda.yaml
```

This mirrors the contents of the local file-system repository to your Anaconda Enterprise installation under the user-name `anaconda`.

Configuring Anaconda Enterprise

After creating the mirror, *edit your Anaconda Enterprise configuration* to add this new mirrored channel to the default Anaconda Enterprise channels and make the packages available to users.

```
conda:
  channels:
    - defaults
  default_channels:
    - main
    - free
    - r
  channel_alias: https://<anaconda.example.com>/repository/conda
```

Replacing `<anaconda.example.com>` with the actual URL to your installation of Anaconda Enterprise.

Note: The `ap-workspace` pod must be restarted for the configuration change to take effect on new project editor sessions.

To update the Anaconda Enterprise server with your changes, you'll need to do the following:

1. Run the following command in an interactive shell to identify the pod associated with the workspace services:

```
kubectl get pods
```

2. Restart the workspace services by running the following command:

```
kubectl delete pod anaconda-enterprise-ap-workspace-<pod ID>
```

Sharing channels

To make your new channels visible to your users in their **Channels** list, you need to share the channels with them.

EXAMPLE: To share new channels `main`, `free`, and `r` with group `everyone` for read access:

```
anaconda-enterprise-cli channels share --group everyone --level r main
anaconda-enterprise-cli channels share --group everyone --level r free
anaconda-enterprise-cli channels share --group everyone --level r r
```

After running the `share` command, verify by logging onto the user interface and viewing the **Channels** list.

For more information, see [Sharing channels and packages](#)

Mirror configuration options

You can use the following options to configure your mirror:

- *Configuring SSL verification.*
- *Mirroring in a proxied environment.*
- *Mirroring specific platforms and versions.*
- *Using blacklisting to exclude packages.*
- *Using whitelisting to include package.*
- *Combining multiple configuration arguments.*

remote_url

Specifies the remote URL from which the conda packages and the Anaconda and Miniconda installers are downloaded. The default value is: `https://repo.continuum.io/`.

channels

Specifies the remote channels from which conda packages are downloaded. The default is a list of the channels `<remote_url>/pkgs/free/` and `<remote_url>/pkgs/pro/`

All specification information should be included in the same file, and can be passed to the `cas-sync-api-v5` command via the `--file` argument:

```
cas-sync-api-v5 --file ~/cas-mirror/etc/anaconda-platform/mirrors/anaconda.yaml
```

destination channel

The configuration option `dest_channel` specifies where files will be uploaded. The default value is: `anaconda`.

SSL verification

The mirroring tool uses two different settings for configuring SSL verification. When the mirroring tool connects to its destination, it uses the `ssl_verify` setting from `anaconda-enterprise-cli` to determine how to validate certificates. For example, to use a custom certificate authority:

```
anaconda-enterprise-cli config set sites.master.ssl_verify /etc/ssl/certs/ca-
↳certificates.crt
```

The mirroring tool uses `conda`'s configuration to determine how to validate certificates when connecting to the source that it is pulling packages from. For example, to disable certificate validation when connecting to the source:

```
conda config --set ssl_verify false
```

Mirroring in a proxied environment

If Anaconda Enterprise 5 is installed in a proxied environment, set the `NO_PROXY` variable. This ensures the mirroring tool does not use the proxy when communicating with the repository service, and prevents errors such as `Max retries exceeded, Cannot connect to proxy, and Tunnel connection failed: 503 Service Unavailable`.

```
export NO_PROXY=<master-node-domain-name>
```

Platform-specific mirroring

By default, the `cas-sync-api-v5` tool mirrors all platforms. If you do not need all platforms, edit the YAML file to specify the platform(s) you want mirrored:

```
platforms:
- linux-64
- osx-64
- win-64
```

Note: The platform argument is evaluated before any other argument.

Package-specific mirroring

In some cases you may want to mirror only a small subset of the repository. Rather than blacklisting a long list of packages you do not want mirrored, you can instead simply enumerate the list of packages you DO want mirrored.

Note: This argument cannot be used with the `blacklist`, `whitelist` or `license_blacklist` arguments—it can only be combined with platform-specific and version-specific mirroring.

EXAMPLE:

```
pkg_list:
- accelerate
- pyqt
- zope
```

This example mirrors only the three packages: Accelerate, PyQt & Zope. All other packages will be completely ignored.

Python version-specific mirroring

Mirror the repository with a Python version or versions specified.

EXAMPLE:

```
python_versions:
- 3.3
```

Mirrors only Anaconda packages built for Python 3.3.

License blacklist mirroring

The mirroring script supports license blacklisting for the following license families:

```
AGPL
GPL2
GPL3
LGPL
BSD
MIT
Apache
PSF
Public-Domain
Proprietary
Other
```

EXAMPLE:

```
license_blacklist:
- GPL2
- GPL3
- BSD
```

This example mirrors all the packages in the repository EXCEPT those that are GPL2-, GPL3-, or BSD-licensed, because those three licenses have been blacklisted.

Blacklist mirroring

The blacklist allows access to all packages EXCEPT those explicitly listed. If the `license_blacklist` and `blacklist` arguments are combined, `license_blacklist` is evaluated first, and `blacklist` is a supplemental modifier.

EXAMPLE:

```
blacklist:
- bzip2
- tk
- openssl
```

This example mirrors the entire repository EXCEPT the `bzip2`, `Tk`, and `OpenSSL` packages.

Whitelist mirroring

The `whitelist` argument adds or includes packages that would be otherwise excluded by the `blacklist` and/or `license_blacklist` functions.

EXAMPLE:

```
license_blacklist:
- GPL2
- GPL3
whitelist:
- readline
```

This example mirrors the entire repository EXCEPT any GPL2- or GPL3-licenses packages, but includes `readline`, despite the fact that it is GPL3-licensed.

Combining multiple mirror configurations

You may find that combining two or more of the arguments above is the easiest way to get the exact combination of packages that you want.

Note: The platform argument is evaluated before any other argument.

EXAMPLE: This example mirrors only Linux-64 distributions of the `dnspython`, `Shapely` and `GDAL` packages:

```
platforms:
- linux-64
pkg_list:
- dnspython
- shapely
- gdal
```

If the `license_blacklist` and `blacklist` arguments are combined, `license_blacklist` is evaluated first, and `blacklist` is a supplemental modifier.

EXAMPLE: In this example, the mirror configuration does not mirror GPL2-licensed packages. It does not mirror the GPL3 licensed package `pyqt` because it has been blacklisted. It does mirror all other packages in the repository:


```
license_blacklist:
- GPL2
blacklist:
- pyqt
```

If the `blacklist` and `whitelist` arguments are both employed, the `blacklist` is evaluated first, with the `whitelist` functioning as a modifier.


EXAMPLE: This example mirrors all packages in the repository except `astropy` and `pygments`. Despite being listed on the `blacklist`, `accelerate` is mirrored because it is listed on the `whitelist`.

```
blacklist:
- accelerate
- astropy
- pygments
whitelist:
- accelerate
```

2.3.3 Managing channels and packages

Anaconda Enterprise makes it easy for you to manage the various channels and packages used by your organization—whether you prefer using the UI or the CLI.


1. Log in to the console using the Administrator credentials required to access the Administrative Console.
2. Select **Channels** in the left menu to view the list of existing channels, each channel's owner and when the channel was last updated.



Channel	Owner	Last Updated
Anaconda	whita	August 5, 2019, 3:15 PM
anaconda	saundramonroe	August 5, 2019, 3:22 PM
anaconda-enterprise	anaconda-enterprise	August 5, 2019, 10:34 AM
🔒 crystal	csqa	August 16, 2019, 9:33 AM
demo2	cgunn	August 5, 2019, 10:28 AM
demo_channel	cgunn	August 5, 2019, 10:29 AM

Note: Private channels are displayed with a lock icon next to their name in the list, to indicate their secure status.


3. Click on a *channel* name to view details about the packages in the channel, including the supported platforms, versions and when each package in the channel was last modified. You can also see the number of times each package has been downloaded.




- To add a package to an existing channel, click **Upload** and browse for the package.

Note: There is a 1GB file size limit for package files you upload.

- Click on a *package* name to view the list of files that comprise the package, and the command used to install the package.




- To remove a package from a channel, select **Delete** from the command menu  for the package in the list.

Warning: The `anaconda-enterprise` channel is used for internal purposes only, and should not be modified.

Sharing channels

To share a public channel, click **Share**, copy the URL location of the channel, and distribute it to the people with whom you want to share the channel.

To give other platform users read-write access to the channel, click **Share** and add them as a collaborator. You can share a channel with individual users or groups of users—the easiest way to control access to a channel. See [Managing roles and groups](#) for more information.



Note: The default is to grant all collaborators read-write access, so if you want to prevent them from adding and removing packages from the channel, be sure they have read-only access. You'll need to [use the CLI](#) to grant read-only access to specific users or groups (see below).

To create a new channel and add packages to the channel for others to access:

1. Click **Create** in the top right corner, enter a meaningful name for the channel and click **Create**.

Note: Channels are `Public`—accessible by non-authenticated users—by default. To make the channel `Private`, and therefore available to authenticated users only, disable the toggle to switch the channel setting from `Public` to `Private`.

2. Click **Upload** to select the packages you want to add to the channel.

Using the CLI:

Get a list of all the channels on the platform with the `channels list` command:

```
anaconda-enterprise-cli channels list
```

Share a channel with a specific user using the `share` command:

```
anaconda-enterprise-cli channels share --user username --level r <channelname>
```

You can also share a channel with an existing group:

```
anaconda-enterprise-cli channels share --group GROUPNAME --level r <channelname>
```

Replacing `GROUPNAME` with the actual name of the group.

Note: Adding `--level r` grants this group read-only access to the channel.

You can “unshare” a channel using the following command:

```
anaconda-enterprise-cli channels share --user <username> --remove <channelname>
```

Run `anaconda-enterprise-cli channels --help` to see more information about what you can do with channels.

For help with a specific command, enter that command followed by `--help`:

```
anaconda-enterprise-cli channels share --help
```

2.3.4 Pointing conda to an on-premises repository

Anaconda Enterprise users who are familiar with `conda` may use it to install the packages they need, rather than rely on you to make them available for download via shared channels.

If your organization wants to limit platform users to only access packages in your on-premises repository, you can configure `conda` accordingly. When you do this at the system level, it overrides any user-level configuration files installed by the user, or on individual machines.

Listing channel locations in the `.condarc` file overrides `conda` defaults, causing `conda` to search only the channels listed, in the order specified.

To configure `conda`, create or update the `~/.condarc` system configuration file in the root directory of the environment to add the repository channel:

```
channel_alias: https://<your-server.domain.com>/repository/conda/
```

Replacing `<your-server.domain.com>` with the fully-qualified domain name (FQDN) of your installation of Anaconda Enterprise.

See [this section of the conda docs](#) for more information.

2.3.5 Using a proxy for conda packages

You can configure Anaconda Enterprise to use a proxy for `conda` packages, if your organization’s network security policy requires it. To do so, you’ll need to do the following:

- *Install Miniconda*
- *Install the Anaconda Enterprise CLI*

- *Configure Anaconda Enterprise*
 - *Verify the proxy works*
-

Installing Miniconda

Install Miniconda, a mini version of Anaconda that includes conda, its dependencies, and Python.

1. Download the Miniconda installer to the current working directory.

Note: If you want the file saved in a different directory, make sure you `cd` to the working directory before running this command.

2. Run the following command to install Miniconda to the root directory (e.g., `~centos/miniconda3`):

```
sh Miniconda3-latest-Linux-x86_64.sh
```

3. Re-initialize your terminal for the previous steps to take effect:

```
source ~/.bashrc
```

4. Whitelist the *local* repository by running the following command to set the `NO_PROXY` environment variable, providing the FQDN of the local repo:

```
export NO_PROXY=https://<your-server.domain.com>
```

Installing and configuring the Anaconda Enterprise CLI

You'll need to use the Anaconda Enterprise CLI in subsequent steps, so install it now if you haven't already done so.

1. Run the following command to install the Anaconda Enterprise CLI and package mirroring tool:

```
conda install -kc https://<your-server.domain.com>/repository/conda/anaconda-  
↪enterprise anaconda-enterprise-cli cas-mirror git
```

2. After the list of package dependencies has been resolved, type `y` to proceed with the installation.
3. To configure the Anaconda CLI, run the following commands, using the FQDN of your Anaconda Enterprise instance:

```
anaconda-enterprise-cli config set sites.master.url https://<your-server.domain.  
↪com>/repository/api  
  
anaconda-enterprise-cli config set default_site master  
  
anaconda-enterprise-cli config set ssl_verify false
```

Configuring Anaconda Enterprise

After you've installed and configured the required tools, you can update your Anaconda Enterprise configuration:

1. Log in to the Operations Center UI at `https://<your-server.domain.com>:32009`, using either the default credentials `aeplatform@anaconda.com / aeplatform` or the credentials of *another Operations Center Admin user*.
2. Click **Configuration** in the menu on the left and use the **Config maps** drop-down menu to select the `anaconda-enterprise-anaconda-platform.yml` configuration file.

Warning: We strongly recommend you **make a manual backup copy of this file before editing it**, as any changes you make will impact how Anaconda Enterprise functions.

3. Scroll down to the `conda` section and ensure it looks like the following:

```
conda: # Common conda settings for editing sessions and deployments
  channels:
    - defaults

    default_channels: # List of channels that should be used for channel 'defaults'
      - https://repo.anaconda.com/pkg/main
      - https://repo.anaconda.com/pkg/free
      - https://repo.anaconda.com/pkg/
```

4. Run this command to access the CLI:

```
anaconda-enterprise-cli login
```

5. Log in using the same username and password that you use to log in the Anaconda Enterprise web interface (or the default Admin credentials `anaconda-enterprise/anaconda-enterprise`).
6. Create a config file (`condarc.secret.txt`) for conda proxying with the following content, and mount it at `/etc/conda/.condarc`:

```
proxy_servers:
  http: http://proxy.url.com:<port>
  https: https://proxy.url.com:<port>
```

7. Run the following command to create a Kubernetes secret:

```
anaconda-enterprise-cli spark-config --config /etc/conda/.condarc condarc.secret.
↩️.txt
```

8. Upload the secret to Kubernetes.

Warning: This will delete any existing custom Kubernetes secrets in `anaconda-config-files-secret.yaml`, so if you've already configured other secrets (e.g., for Hadoop Spark access) make sure you include those secrets and move the existing file to a remote location to preserve it.

9. Restart the relevant pods:

```
sudo gravity enter
kubectl get pods | grep 'ap-deploy\|ap-workspace\|ap-ui' | cut -d' ' -f1 | xargs_
↪ kubectl delete pods
```

Verifying the proxy works

After you've configured the platform, you can test your changes to verify that it's using the proxy.

1. Log into Anaconda Enterprise.
2. Click **Projects**, and open the project you want to use to test the proxy.

Note: If the project already has an open session, you'll need to stop the current session and start a new session.

3. Open a terminal window within JupyterLab and run the following command to display the conda configuration:

```
conda config --show
```

4. Verify the proxy config information from `condarc.secret.txt` is being set.
5. Run the following command to prepare the project:

```
anaconda-project prepare
```

Packages should be resolving and being pulled from public Anaconda repositories.

2.4 Generating custom Anaconda installers

As an Anaconda Enterprise Administrator, you can *create custom environments*. These environments include specific packages and their dependencies. You can then *create a custom installer* for the environment, that can be shipped to HDFS and used in Spark jobs.


Custom installers enable IT and Hadoop administrators to maintain close control of a Hadoop cluster while also making these tools available to data scientists who need Python and R libraries. They provide an easy way to ship multiple custom Anaconda distributions to multiple Hadoop clusters.

2.4.1 Creating an environment

1. Log in to the console using the Administrator credentials *configured after installation*.
2. Select **Environments** in the left menu.
3. Click **Create** in the upper right corner, give the environment a unique name and click **Save**.


Note: Environment names can contain alphanumeric characters and underscores only.

4. Check the channel you want to choose packages from, then select the specific packages—and version of each—you want to include in the installer.



5. Click **Save** in the window banner to create the environment.

Anaconda Enterprise resolves all the package dependencies and displays the environment in the list. If there is an issue resolving the dependencies, you'll be notified and prompted to edit the environment.




You can now use the environment as a basis for creating additional versions of the environment or other environments.

To edit an existing environment:

1. Click on an environment name to view details about the packages included in the environment, then click **Edit**.
2. Change the channels and/or packages included in the environment, and enter a version number for the updated package before clicking **Save**. The new version is displayed in the list of environments.


To copy an environment:

1. Select the environment in the list and click the **Duplicate Environment** icon .
2. Enter a unique name for the environment and click **Save**. The new environment is displayed in the list of environments.


Now that you've created an environment, you can create an installer for it.


2.4.2 Creating a custom installer for an environment

1. Select the environment in the list, click the **Create installer** icon , and select the type of installer you want to create:



Anaconda Enterprise creates the installer and displays it in the **Installers** list:



2. To view the relevant logs, download or delete the installer, click the  icon and choose the appropriate command.


If you created a *management pack*, you'll need to install it on your Hortonworks HDP cluster and add it to your local Ambari server to make it available to users. For more information, see [this blog post about generating custom management packs](#).

If you created a *parcel*, you'll need to install it on your Cloudera CDH cluster to make it available to users:


Note: If you are using CDH 5.x, you'll need to manually download the parcel, move it to the Cloudera Manager node, then configure Cloudera Manager for a *local* parcel repository. This is because CDH 5.x does not work with TLS 1.2 that Anaconda Enterprise uses to serve the parcel, so you'll see a protocol version error if you attempt to use AE as a *remote* parcel repository with CDH 5.x.

If you are using CDH 6.x with parcels, you can configure Anaconda Enterprise as a remote parcel repository, or you can manually download the parcel and configure a local parcel repository.

1. In the **Installers** list, click the parcel name to view its details—including the logs generated during the creation process.



2. Depending on the version of CDH you are using (see NOTE above), either copy the path to the parcel or download the parcel installer.
3. From the *Cloudera Manager Admin Console*, click the **Parcels** indicator in the top navigation bar.
4. Click the **Configuration** button on the top right of the **Parcels** page to display the **Parcel Settings**.



- If you downloaded the parcel from AE in Step 2 above, copy it to the **Local Parcel Repository Path** you've configured for Cloudera Manager.

—or—

To configure AE as a remote parcel repository, add the URL you copied in Step 2 above to the **Remote Parcel Repository URLs** section and click **Save Changes**.


If automatic downloading and distribution are not enabled, go to the **Parcels** page and select **Distribute** to install the parcel across your CDH cluster. The custom-generated Anaconda parcel is now ready to use with Spark or other distributed frameworks on your Cloudera CDH cluster.

For more information, see [these instructions from Cloudera](#).

2.5 Advanced platform settings

After installing Anaconda Enterprise, there are default settings that you may want to update with information specific to your installation, including the *password for the database* and the *redirect URLs* for the AE platform.

- If you've *installed Livy server*, you'll need to *configure it to work with the platform* so users can access your Hadoop Spark cluster.
- If your organization already uses a repository such as GitHub, Bitbucket, or GitLab for version control, you can *configure Anaconda Enterprise to use that repository* instead of the internal Git server.
- You can also *add one or more NFS shares* to your organization's configuration, for platform users to store data and source code that they can access within their sessions and deployments.
- You may want to replace the self-signed certificates generated during installation with your organization's own certificates—or change other default security settings—after initial installation.




2.5.1 Editing platform settings

You configure the Anaconda Enterprise platform settings using a configuration file or *Config map*. The configuration file, `anaconda-enterprise-anaconda-platform.yml`, contains both global and per-service configuration settings for your Anaconda Enterprise installation.

You can modify the default configuration using the Operations Center UI, or a command shell. Any changes you make will impact how Anaconda Enterprise functions, so **we strongly recommend that you save a copy of the original file** and familiarize yourself with the configuration options before making any changes.

To modify the platform configuration using the UI:

1. Log in to Anaconda Enterprise, select the **Menu** icon  in the top right corner and click the **Administrative Console** link displayed at the bottom of the slide out window.
2. Click **Manage Resources**.
3. Log in to the Operations Center using the Administrator credentials *configured after installation*.
4. Select **Configuration** from the menu on the left.
5. Use the **Config map** drop-down menu to select the `anaconda-enterprise-anaconda-platform.yml` configuration file.

Warning: Unless you want to *configure global environment variables*, **please ignore the other entries in the Config maps and Namespace drop-downs**. They impact the underlying Kubernetes system, so making changes to them may have unintended consequences or cause the platform to behave unpredictably.

You'll notice that it contains GLOBAL CONFIGURATION specifications related to the following:

- The Authentication Center client URL
- The internal database
- Optional NFS server volume mounts
- HTTPS certificate settings
- Resource profiles
- The Kubernetes cluster
- Any users, groups or roles with Admin authorization
- The git commit file size limit (The default limit is 50MB, though this limit is configurable. We recommend keeping files under 100MB.)

It also contains PER-SERVICE CONFIGURATION settings, related to these services:

- The authentication server used to secure access
 - The deployment server used to deploy apps
 - The workspace server used to run sessions
 - The storage server used to store and version projects
 - The local repository server used for channels and packages
 - The S3 endpoint and Git server used to store object and data
 - The local documentation server URL and platform UI configuration
6. Edit the specification in the section that corresponds to the setting you want to update, and click **Apply** to save your changes.

Note: If you navigate away from the Config map without saving your edits, you will be warned that you have unsaved changes. You can abandon your edits by clicking **Disregard and continue**, or return to editing by clicking **Close**.

To edit the platform configuration using a command line:

1. Enter the following commands in an interactive shell *on the master node*:

```
sudo gravity enter
kubectl edit cm anaconda-enterprise-anaconda-platform.yml
```

2. Make your changes to the file, and save it.
3. Restart all pods using the following command:

```
kubectl get pods | grep ap- | cut -d' ' -f1 | xargs kubectl delete pods
```

2.5.2 Changing the database password

You can change the password for the Anaconda Enterprise database as needed, to adhere to your organization's policies. To do so, you'll need to connect to the associated pod, make the change, and update the platform with the new password.

1. Run the following command to determine the id of the postgres pod:

```
kubectl get pod | grep postgres
```

2. Run the following command to connect to the postgres pod, where `<id>` represents the id of the pod:

```
kubectl exec -it anaconda-enterprise-postgres-<id> /bin/sh
```

3. Run this `psql` command to connect to the database:


```
psql -h localhost -U postgres
```

4. Set the password by running the following command:

```
ALTER USER postgres WITH PASSWORD 'new_password';
```

To update the platform settings with the database password of the host server:

1. Access the Anaconda Enterprise Operations Center by entering this URL in your browser: `https://anaconda.example.com:32009`, replacing `anaconda.example.com` with the FQDN of the host server.
2. Login with the default username and password: `aeplatform@yourcompany.com/aeplatform`. You'll be asked to change the default password when you log in.
3. Click **Configuration** in the left menu to display the Anaconda Enterprise Config map.
4. In the GLOBAL CONFIGURATION section of the configuration file, locate the `db` section and enter the password you just set:



5. Click **Apply** to update the platform with your changes.
6. Restart all the service pods using the following command:

```
kubectl get pods | grep ap- | cut -d' ' -f1 | xargs kubectl delete pods
```

2.5.3 Changing the platform redirect URLs

You'll use the Anaconda Enterprise Authentication Center to update the redirect URLs for the platform.

1. Enter the following URL in your browser, `https://<server-name.domain.com>/auth/`, replacing `server-name.domain.com` with the fully-qualified domain name of the host server.
2. Login with username and password configured to authorize access to the platform. See [Managing System Administrators](#) for instructions on setting these credentials, if you haven't already done so.
3. Verify that `AnacondaPlatform` is displayed as the current realm, then select **Clients** from the **Configure** menu on the left.

Client ID	Enabled	Base URL	Actions
account	True	/auth/realm/AnacondaPlatform/account	Edit Export Delete
admin-cl	True	Not defined	Edit Export Delete
anaconda-deploy	True	Not defined	Edit Export Delete
anaconda-deploy-proxy	True	Not defined	Edit Export Delete
anaconda-enterprise-notebooks	True	Not defined	Edit Export Delete
anaconda-platform	True	https://beta.dev.anaconda.com	Edit Export Delete
anaconda-repository	True	Not defined	Edit Export Delete
anaconda-workspace	True	Not defined	Edit Export Delete
anaconda-workspace-api	True	Not defined	Edit Export Delete

4. In the **Clients** list, click `anaconda-platform` to display the platform settings.
5. On the **Settings** tab, update all URLs in the following fields with the FQDN of the Anaconda Enterprise server, or the following symbols:

Note: If you choose to provide the FQDN of your AE server, be sure each field also ends with the symbols shown. For example, the **Valid Redirect URIs** would look something like this: `https://server-name.domain.com/*.`

6. Click **Save** to update the server with your changes.

Root URL

* Valid Redirect URIs

Base URL

Admin URL

Web Origins

> Fine Grain OpenID Connect Configuration

Save Cancel

2.5.4 Configuring Livy server for Hadoop Spark access

After *installing Livy server*, there are main 3 aspects you need to configure on Apache Livy server for Anaconda Enterprise users to be able to access Hadoop Spark within Anaconda Enterprise:

- *Livy impersonation*
- *Cluster access*
- *Project access*

If the Hadoop cluster is configured to use Kerberos authentication, you'll need to *allow Livy to access the services*. Additionally, you can configure Livy as a secure endpoint. For more information, see *Configuring Livy to use HTTPS* below.

Configuring Livy impersonation

To enable users to run Spark sessions within Anaconda Enterprise, they need to be able to log in to each machine in the Spark cluster. The easiest way to accomplish this is to configure Livy impersonation as follows:

1. Add `Hadoop.proxyuser.livy` to your authenticated hosts, users, or groups.
2. Check the option to `Allow Livy to impersonate users` and set the value to `all (*)`, or a list of specific users or groups.

If impersonation is *not* enabled, the user executing the `livy-server` (`livy`) must exist on every machine. You can add this user to each machine by running the following command on each node:

```
sudo useradd -m livy
```

Note: If you have any problems configuring Livy, try setting the log level to `DEBUG` in the `conf/log4j.properties` file.

Configuring cluster access

Livy server enables users to submit jobs from any remote machine or analytics cluster—even where a Spark client is not available—without requiring you to install Jupyter and Anaconda directly on an edge node in the Spark cluster.

To configure Livy server, put the following environment variables into a user's `.bashrc` file, or the `conf/livy-env.sh` file that's used to configure the Livy server.

These values are accurate for a Cloudera install of Spark with Java version 1.8:

```
export JAVA_HOME=/usr/java/jdk1.8.0_121-cloudera/jre/
export SPARK_HOME=/opt/cloudera/parcels/CDH/lib/spark/
export SPARK_CONF_DIR=$SPARK_HOME/conf
export HADOOP_HOME=/etc/hadoop/
export HADOOP_CONF_DIR=/etc/hadoop/conf
```

Note that the port parameter that's defined as `livy.server.port` in `conf/livy-env.sh` is the same port that will generally appear in the Sparkmagic user configuration.

The minimum required parameter is `livy.spark.master`. Other possible values include the following:

- `local[*]`—for testing purposes
- `yarn-cluster`—for using with the YARN resource allocation system
- a full spark URI like `spark://masterhost:7077`—if the spark scheduler is on a different host.

Example with YARN:

```
livy.spark.master = yarn-cluster
```

The YARN deployment mode is set to `cluster` for Livy. The `livy.conf` file, typically located in `$LIVY_HOME/conf/livy.conf`, may include settings similar to the following:

```
livy.server.port = 8998
# What spark master Livy sessions should use: yarn or yarn-cluster
livy.spark.master = yarn
# What spark deploy mode Livy sessions should use: client or cluster
livy.spark.deployMode = cluster

# Kerberos settings

livy.server.auth.type = kerberos
livy.impersonation.enabled = true

# livy.server.launch.kerberos.principal = livy/$HOSTNAME@ANACONDA.COM
# livy.server.launch.kerberos.keytab = /etc/security/livy.keytab
# livy.server.auth.kerberos.principal = HTTP/$HOSTNAME@ANACONDA.COM
# livy.server.auth.kerberos.keytab = /etc/security/httplivy.keytab

# livy.server.access_control.enabled = true
# livy.server.access_control.users = livy,hdfs,zeppelin
# livy.superusers = livy,hdfs,zeppelin
```

After configuring Livy server, you'll need to restart it:

```
./bin/anaconda-livy-server stop
./bin/anaconda-livy-server start
```

Consider using a process control mechanism to restart Livy server, to ensure that it's reliably restarted in the event of a failure.

Using Livy with Kerberos authentication

If the Hadoop cluster is configured to use Kerberos authentication, you'll need to do the following to allow Livy to access the services:

1. Generate 2 keytabs for Apache Livy using `kadmin.local`.

IMPORTANT: The keytab principals for Livy must match the hostname that the Livy server is deployed on, or you'll see the following exception: `GSSEException: No valid credentials provided (Mechanism level: Failed to find any Kerberos credentials)`.

These are hostname and domain dependent, so edit the following example according to your Kerberos settings:

```
$ sudo kadmin.local

kadmin.local: addprinc livy/ip-172-31-3-131.ec2.internal
WARNING: no policy specified for livy/ip-172-31-3-131.ec2.internal@ANACONDA.COM;
↳defaulting to no policy
Enter password for principal "livy/ip-172-31-3-131.ec2.internal@ANACONDA.COM":
Re-enter password for principal "livy/ip-172-31-3-131.ec2.internal@ANACONDA.COM":
kadmin.local: xst -k livy-ip-172-31-3-131.ec2.internal.keytab livy/ip-172-31-3-131.
↳ec2.internal@ANACONDA.COM
...

kadmin.local: addprinc HTTP/ip-172-31-3-131.ec2.internal
WARNING: no policy specified for HTTP/ip-172-31-3-131.ec2.internal@ANACONDA.COM;
↳defaulting to no policy
Enter password for principal "HTTP/ip-172-31-3-131.ec2.internal@ANACONDA.COM":
Re-enter password for principal "HTTP/ip-172-31-3-131.ec2.internal@ANACONDA.COM":
kadmin.local: xst -k HTTP-ip-172-31-3-131.ec2.internal.keytab HTTP/ip-172-31-3-131.
↳ec2.internal@ANACONDA.COM
...
```

This will generate two files: `livy-ip-172-31-3-131.ec2.internal.keytab` and `HTTP-ip-172-31-3-131.ec2.internal.keytab`.

2. Change the permissions of these two files so they can be read by `livy-server`.
3. Enable Kerberos authentication and reference these two keytab files in the `conf/livy.conf` configuration file, as shown:

```
livy.server.auth.type = kerberos
livy.impersonation.enabled = false # see notes below

# principals and keytabs to exactly match those generated before
livy.server.launch.kerberos.principal = livy/ip-172-31-3-131@ANACONDA.COM
livy.server.launch.kerberos.keytab = /home/centos/conf/livy-ip-172-31-3-131.keytab
livy.server.auth.kerberos.principal = HTTP/ip-172-31-3-131@ANACONDA.COM
livy.server.auth.kerberos.keytab = /home/centos/conf/HTTP-ip-172-31-3-131.keytab

# this may not be required when delegating auth to kerberos
livy.server.access-control.enabled = true
livy.server.access-control.allowed-users = livy,zeppelin,testuser
livy.superusers = livy,zeppelin,testuser
```

NOTES:

- The hostname and domain are not the same—verify that they match your Kerberos configuration.
- `livy.server.access-control.enabled = true` is only required if you're going to also whitelist the allowed users with the `livy.server.access-control.allowed-users <user> key`.

Configuring project access

After you’ve installed Livy and configured cluster access, some additional configuration is required before Anaconda Enterprise users will be able to connect to a remote Hadoop Spark cluster from within their projects. For more information, see [Connecting to the Hadoop Spark ecosystem](#).

- If the Hadoop installation used Kerberos authentication, add the `krb5.conf` to the global configuration using the following command:

```
anaconda-enterprise-cli spark-config --config /etc/krb5.conf krb5.conf
```

- To use Sparkmagic, pass two flags to the previous command to configure a Sparkmagic configuration file:

```
anaconda-enterprise-cli spark-config --config /etc/krb5.conf krb5.conf --config /  
↪opt/continuum/.sparkmagic/config.json config.json
```

This creates a yaml file—`anaconda-config-files-secret.yaml`—with the data converted for Anaconda Enterprise.

Use the following command to upload the yaml file to the server:

```
sudo kubectl replace -f anaconda-config-files-secret.yaml
```

To update the Anaconda Enterprise server with your changes, run the following command to identify the pod associated with the workspace services:

```
kubectl get pods
```

Restart the workspace services by running:

```
kubectl delete pod anaconda-enterprise-ap-workspace-<unique ID>
```

Now, whenever a new project is created, `/etc/krb5.conf` will be populated with the appropriate data.

Configuring Livy to use HTTPS

If you want to use Sparkmagic to communicate with Livy via HTTPS, you need to do the following to configure Livy as a secure endpoint:

- Generate a keystore file, certificate, and truststore file for the Livy server—or use a third-party SSL certificate.
- Update Livy with the keystore details.
- Update your Sparkmagic configuration.
- Restart the Livy server.

If you’re using a self-signed certificate:

1. Generate a keystore file for Livy server using the following command:

```
keytool -genkey -alias <host> -keyalg RSA -keysize 1024 -dname CN=<host>,OU=hw,  
↪O=hw,L=paloalto,ST=ca,C=us -keypass <keyPassword> -keystore <keystore_file> -  
↪storepass <storePassword>
```

2. Create a certificate:

```
keytool -export -alias <host> -keystore <keystore_file> -rfc -file <cert_file> -  
↪storepass <StorePassword>
```

3. Create a truststore file:

```
keytool -import -noprompt -alias <host> -file <cert_file> -keystore <truststore_  
↪file> -storepass <truststorePassword>
```

4. Update livy.conf with the keystore details. For example:

```
livy.keystore = /home/centos/livy-0.5.0-incubating-bin/keystore.jks  
livy.keystore.password = anaconda  
livy.key-password = anaconda
```

5. Update ~/.sparkmagic/config.json. For example:

```
"kernel_python_credentials" : {  
  "username": "",  
  "password": "",  
  "url": "https://35.172.121.109:8998",  
  "auth": "None"  
},  
"ignore_ssl_errors": true,
```

Note: In this example, `ignore_ssl_errors` is set to `true` because this configuration uses self-signed certificates. Your production cluster setup may be different.

Warning: If you misconfigure a `.json` file, all Sparkmagic kernels will fail to launch. You can test your Sparkmagic configuration by running the following Python command in an interactive shell: `python -m json.tool config.json`.

If you have formatted the JSON correctly, this command will run without error. Additional edits may be required, depending on your Livy settings.

6. Restart the Livy server.

The Livy server should now be accessible over https. For example, `https://<livy host>:<livy port>`.

To test your SSL-enabled Livy server, run the following Python code in an interactive shell to create a session:

```
livy_url = "https://<livy host>:<livy port>/sessions"  
data = {'kind': 'spark', 'numExecutors': 1}  
headers = {'Content-Type': 'application/json'}  
r = requests.post(livy_url, data=json.dumps(data), headers=headers,  
↪auth=HTTPKerberosAuth(mutual_authentication=REQUIRED, sanitize_mutual_error_  
↪response=False), verify=False)  
r.json()
```

Run the following Python code to verify the status of the session:

```
session_url = "https://<livy host>:<livy port>/sessions/0"
headers = {'Content-Type': 'application/json'}
r = requests.get(session_url, headers=headers, auth=HTTPKerberosAuth(mutual_
↪ authentication=REQUIRED, sanitize_mutual_error_response=False), verify=False)
r.json()
```

Then submit the following statement:

```
session_url = "https://<livy host>:<livy port>/sessions/0/statements"
data = {"code": "sc.parallelize(1 to 10).count()"}
headers = {'Content-Type': 'application/json'}
r = requests.get(session_url, headers=headers, auth=HTTPKerberosAuth(mutual_
↪ authentication=REQUIRED, sanitize_mutual_error_response=False), verify=False)
r.json()
```

If you're using a third-party certificate:

Note: Ensure that [Java JDK](#) is installed on the Livy server.

1. Create the `keystore.p12` file using the following command:

```
openssl pkcs12 -export -in [path to certificate] -inkey [path to private key] -
↪ certfile [path to certificate ] -out keystore.p12
```

2. Use the following command to create the `keystore.jks` file:

```
keytool -importkeystore -srckeystore keystore.p12 -srcstoretype pkcs12 -
↪ destkeystore keystore.jks -deststoretype JKS
```

3. If you don't already have the `rootca.crt`, you can run the following command to extract it from your Anaconda Enterprise installation:

```
kubectl get secrets anaconda-enterprise-certs -o jsonpath="{.data[\"rootca.crt\"]}"
↪ " | base64 -d > /ext/share/rootca.crt
```

4. Add the `rootca.crt` to the `keystore.jks` file:

```
keytool -importcert -keystore keystore.jks -storepass <password> -alias rootCA -
↪ file rootca.crt
```

5. Add the `keystore.jks` file to the `livy.conf` file. For example:

```
livy.keystore = /home/centos/livy-0.5.0-incubating-bin/keystore.jks
livy.keystore.password = anaconda
livy.key-password = anaconda
```

6. Restart the Livy server.
7. Run the following command to verify that you can connect to the Livy server (using your actual host and port):

```
openssl s_client -connect anaconda.example.com:8998 -CAfile rootca.crt
```

If running this command returns 0, you've successfully configured Livy to use HTTPS.

To add the trusted root certificate to the AE server, do the following:

1. Install the `ca-certificates` package:

```
yum install ca-certificates
```

2. Enable dynamic CA configuration:

```
update-ca-trust force-enable
```

3. Add your `rootca.crt` as a new file:

```
cp rootca.crt /etc/pki/ca-trust/source/anchors
```

4. Update the certificate authority trust:

```
update-ca-trust extract
```

To connect to Livy within a session, open the project and run the following command in an interactive shell:

```
import os
os.environ['REQUESTS_CA_BUNDLE'] = /path/to/root.ca
```

You can also edit the `anaconda-project.yml` file for the project and set the environment variable there. See [Hadoop / Spark](#) for more information.

2.5.5 Connecting to an external version control repository

If your organization already uses a shared repository for version control, you can configure Anaconda Enterprise to use that repository instead of the internal Git server. To associate an external repository with Anaconda Enterprise, you simply need to provide the information required to connect to it.

After you do so, platform users will be able to access the repository within their sessions and deployments without having to leave the platform. Anaconda Enterprise creates a repository for each project that's created by platform users.

Anaconda Enterprise supports integration with the following external repositories:

External repository	Supported versions
Bitbucket Enterprise	5.9.1, 5.12.1, and 6.2.0
Bitbucket Cloud	bitbucket.org
GitHub Enterprise	2.15, 2.16, and 2.17
GitHub Cloud	github.com
GitLab Enterprise	10.4.2, 10.7.1, 11.10.0, and 12.1.6
GitLab Cloud	gitlab.com

Warning: If you are going to use an external repository for version control, we strongly recommend you set it up *before users start creating projects in Anaconda Enterprise*. **If your organization changes Git hosting services, and you therefore need to migrate projects from one version control repository to another**, we recommend you *follow the process outlined here*.


NOTES:

- Neither Bitbucket.com or GitLab.com support versioning of archive downloads and app deployments. In other words, **the latest revision will always be downloaded or deployed**.
- To provide permission granularity and maintain parity with your Git hosting solution, Anaconda Enterprise will grant individual platform users access to individual repositories. **To prevent default permissions being applied to all users within a group, users cannot belong to the given organization or group.**
- Platform users will be prompted for their personal access token *before they create their first project* in Anaconda Enterprise. We recommend you **advise users to create an ever-lasting token**, so they can retain permanent access to their files from within Anaconda Enterprise. The **specific auth token permissions required for each repository** are outlined *here*.

Before you begin, gather the following information:


- The fully qualified domain name (FQDN) of your versions control server
- The organization, team or group name associated with your service account
- The username of the Administrator for the organization, team or group. **This user will require full Admin permissions.**
- The personal access token or password required to connect to your version control repository

To associate a specific version control repository with a project:


1. Log in to Anaconda Enterprise, select the **Menu** icon  in the top right corner and click the **Administrative Console** link displayed at the bottom of the slide out window.
2. Click **Manage Resources**.
3. Log in to the Operations Center using the Administrator credentials *configured after installation*.
4. Select **Configuration** from the menu on the left.
5. Use the **Config map** drop-down menu to select the `anaconda-enterprise-anaconda-platform.yml` configuration file.

Warning: Please ignore the other entries in the **Config maps** and **Namespace** drop-downs. They impact the underlying Kubernetes system, so making changes to them may have unintended consequences or cause the platform to behave unpredictably.

6. Locate the `git` section of the configuration file. The default behavior is to use the internal Anaconda Enterprise repository for version control (see default settings pictured below).



7. To override this default setting, *uncomment* the Example external repo configuration section of the Config map, and replace the placeholder settings with the correct values for your organization's repository:



Where:

`name` = A descriptive name for the service your organization uses.

`type` = The type of version control repository your organization uses: `github-v3-api` (GitHub Enterprise and Cloud), `bitbucket-v1-api` (Bitbucket Server), `bitbucket-v2-api` (Bitbucket Cloud), or `gitlab-v4-api` (GitLab Cloud and GitLab server).

NOTE: The values for this parameter have changed from AE 5.3.0.

`url` = The URL of the API (e.g., <https://api.github.com/>, <https://api.bitbucket.org>, or <https://gitlab.com>).

`credential-url` = The URL to authenticate against for repository operations such as cloning and pushing.

NOTE: This parameter replaces the `credential-hostname` parameter used in AE 5.3.0.


`repository` = Must be `'{owner}-{id}'` encased in single quotes.

`organization` = The name of your Github organization, Bitbucket team, or GitLab group. (*Bitbucket does not support dashes in team names.*)

`username` = The username associated with the Administrator account at Github, Bitbucket, or GitLab. **This account must have full Admin permissions.**

`auth-token` = The Github personal access token, Bitbucket app password, or GitLab access token **for the Administrator account** associated with the username. (*You must enable 2FA to get personal access tokens in GitLab.*)

8. *Comment out* the `Internal repo configuration` section of the Config map that follows, as it relates to the Anaconda Enterprise internal Git server settings that you are overriding:



9. Click **Apply** to save your changes to the Config map.

10. To update the Anaconda Enterprise server with your changes, restart services by running these commands *on the master node*:

```
sudo gravity enter
kubectl get pods | grep ap- | cut -d' ' -f1 | xargs kubectl delete pods
```

To verify that Anaconda Enterprise users can access the version control repository you added, create a project. See [Working with projects](#) for more information.

2.5.6 Migrating projects between version control repositories

If your organization has changed Git hosting services, and you therefore need to migrate projects from one *supported* version control repository to another, we recommend you follow this high-level process:

1. *Perform pre-migration setup.*
2. *Run the project migration script.*
3. *Perform post migration cleanup.*

Prerequisites:

- *Update the Anaconda Enterprise config map* with the information required to connect to the external version control repository.

- To run the project migration script, you'll need Administrator access to a command line tool that can run bash or Python scripts *on the master node of the Anaconda Enterprise cluster*.
- You'll also need the Postgres database password, origin Git host token/password, and destination Git host token/password.

Pre-migration setup

1. If you haven't already done so, install the version of conda provided with the Anaconda Enterprise installer *on the master node*:

```
bash anaconda-enterprise-5.3.1-56.gf54c3abad/installer/conda-bootstrap-4.5.12
```

2. After conda is finished installing, login to the terminal again.
3. Install git, using the command that's appropriate for your environment:

On RHEL/CentOS: `yum install git`

On Ubuntu/Debian: `apt install git`

4. Use the following command to create the conda environment:

```
conda create --name migrate --file anaconda-enterprise-5.3.1-56.gf54c3abad/
↳environment.txt
```

5. Use the following command to activate the conda environment:

```
conda activate migrate
```

6. Temporarily disable reverse proxy authentication by adding the following key-value pair to the `git` section (outside of the `storage` section in the config map) of the `anaconda-enterprise-anaconda-platform.yml` file used to *configure the platform to use an external version control repository*:

```
reverse-proxy-auth: false
```

This should look similar to the following:

```
451 git:
452   url: https://aaron-541-timeout.svc.anaconda.com/platform/git # externally visible URL of the git server
453   host: aaron-541-timeout.svc.anaconda.com # full hostname of the git server
454   port: 8088
455   https:
456     key: /etc/secrets/certs/tls.key
457     certificate: /etc/secrets/certs/tls.crt
458   db:
459     database: anaconda_git
460     directory: /export # directory where git server will store its data
461     username: anaconda # OS username that the git server should run under
462     reverse-proxy-auth: false
463   lfs-secret: AohzzmIZVHYSTYJ7HM1E1GWhjRYCTcFLdxHHGR8FKCM # LFS authentication token secret. Should be uniquely generated for each installation.
464   secret-key: E3P99Z3XRAXaoJHGygmCjZ613pIZ9nvg6SnVRrPHTBU # git server secret key. Should be uniquely generated for each installation.
465   max-commit-file-size: 50000000
466
467
```

7. Run the following command to restart the associated pod on the master node:

```
kubectl delete pod -l 'app=ap-git-storage'
```

8. Create a user mappings file that maps Anaconda Enterprise user IDs to Git user IDs. This is a colon-separated text file where the first field is the AE user name, and the second field is the corresponding Git user name. For example:

```
ae-admin:git-admin
ae-user1:git-user1
ae-user2:git-user2
```

Using the migration tool

Note: If you’ve migrated to <https://github.com>, whenever a user is *added to a project as a collaborator*, they’ll be sent an invitation to collaborate via email. **They’ll need to accept this invitation to be able to commit changes to the repository associated with the project.** *This does not apply to Github Enterprise.*

The migration tool is a Python script, `migrate_projects.py`, found in the AE5 installation tarball. It can be used in the following ways:

```
usage: migrate_projects.py [-h] [--parallel PARALLEL] [--log-file LOG_FILE]
                          [--force-migrate] [--scratch-dir SCRATCH_DIR]
                          --postgres-host POSTGRES_HOST
                          [--postgres-user POSTGRES_USER]
                          [--postgres-passwd POSTGRES_PASSWD]
                          [--origin-api-type {internal,bitbucket-v1-api,bitbucket-v2-api,
↪github-v3-api,gitlab-v4-api}]
                          --origin-api-url ORIGIN_API_URL
                          [--origin-username ORIGIN_USERNAME]
                          [--origin-token ORIGIN_TOKEN]
                          [--origin-organization ORIGIN_ORGANIZATION]
                          [--dest-api-type {internal,bitbucket-v1-api,bitbucket-v2-api,
↪github-v3-api,gitlab-v4-api}]
                          --dest-api-url DEST_API_URL
                          [--dest-username DEST_USERNAME]
                          [--dest-token DEST_TOKEN]
                          [--dest-organization DEST_ORGANIZATION]
                          --dest-user-mappings DEST_USER_MAPPINGS

optional arguments:
-h, --help            show this help message and exit
--parallel PARALLEL   Number of parallel migration jobs to spawn
--log-file LOG_FILE   Path prefix to log directory, suffixed with a
                      timestamp, e.g. migrate-projects-
                      log-1559234750640867208
--force-migrate       Forces migration by replacing local and destination
                      repositories
--scratch-dir SCRATCH_DIR
                      The scratch directory for cloning project repositories
--postgres-host POSTGRES_HOST
                      Hostname of AE5 Postgres DB
--postgres-user POSTGRES_USER
                      Username of AE5 postgres DB
--postgres-passwd POSTGRES_PASSWD
                      Password of AE5 postgres DB
--origin-api-type {internal,bitbucket-v1-api,bitbucket-v2-api,github-v3-api,gitlab-v4-
↪api}
```

(continues on next page)

(continued from previous page)

```

                Origin git host API type
--origin-api-url ORIGIN_API_URL
                Origin git host API URL
--origin-username ORIGIN_USERNAME
                Origin git host username
--origin-token ORIGIN_TOKEN
                Origin git host auth token
--origin-organization ORIGIN_ORGANIZATION
                Origin git host organization
--dest-api-type {internal,bitbucket-v1-api,bitbucket-v2-api,github-v3-api,gitlab-v4-
↪api}
                Destination git host API type
--dest-api-url DEST_API_URL
                Destination git host API URL
--dest-username DEST_USERNAME
                Destination git host username
--dest-token DEST_TOKEN
                Destination git host auth token
--dest-organization DEST_ORGANIZATION
                Destination git host organization
--dest-user-mappings DEST_USER_MAPPINGS
                Colon-separated AE-to-git-host mappings file, e.g. ae-
                user1:github-user1

```

For example, the tool can be used in the following way:

```

python migrate_projects.py --postgres-host localhost --origin-api-url https://
↪localhost:8443/ --origin-username root --dest-api-type gitlab-v4-api --dest-api-url
↪https://mbrock-gitlab.anacondaenterprise.com/ --dest-username root --dest-
↪organization demo --dest-user-mappings user-mappings-gitea-to-gitlab.txt --force-
↪migrate --parallel 4

```

To ensure tokens are not visible in bash history, they can be omitted and can be entered via stdin when running the script.

Post-migration cleanup

After the script finishes migrating the projects, re-enable reverse proxy authentication by editing the key-value pair you previously added to the `git` section of the `anaconda-enterprise-anaconda-platform.yml` file, so it looks like the following:

```
reverse-proxy-auth: true
```

Warning: If you do not re-enable reverse proxy authentication, Anaconda Enterprise will not work.

To verify that the new repository is being used by Anaconda Enterprise, *edit an existing project* and *commit your changes to it*.


2.5.7 Mounting an NFS share

Anaconda Enterprise enables you to specify NFS shares that platform users can use to store data and source code, that they can access within sessions and deployments. You can add an NFS share to Anaconda Enterprise by editing the platform's Config map.


Before you begin:

- The NFS share is mounted using the `anaconda` service account on the Anaconda Enterprise server. To mount the share as writable, configure the NFS server so that the `anaconda` user account (UID 16, by default) has write permissions.
- You'll be editing the Anaconda Enterprise Config map directly, so we recommend you back up the current version of `anaconda-enterprise-anaconda-platform.yml` before making changes to it.

To add an NFS volume mount to the Config map:

1. Log in to Anaconda Enterprise, select the **Menu** icon  in the top right corner and click the **Administrative Console** link displayed at the bottom of the slide out window.
2. Click **Manage Resources**.
3. Log in to the Operations Center using the Administrator credentials *configured after installation*.
4. Select **Configuration** from the menu on the left.
5. Use the **Config map** drop-down menu to select the `anaconda-enterprise-anaconda-platform.yml` configuration file.

The configuration file's `volumes` section provides examples for mounting NFS volumes:




The name of the volume section determines the path where the volume will be mounted. To mount an additional volume, create a second section and give it a unique name. For example, let's say your NFS server has two mount points configured in `/etc/exports` as follows:

```
/small 192.168.1.0/255.255.255.0(rw,sync,no_root_squash)
/large 192.168.1.0/255.255.255.0(rw,sync,no_root_squash)
```

...and you want to mount them as `/data/nfs-small` (read-only) and `/data/nfs-large` (read-write).

Note: Only *lowercase* alphanumeric characters and – dashes are allowed in volume names.

- Uncomment this section of the Config map, and enter the IP address and path to the shared directories on your NFS server as follows:



- Click **Apply** to save your changes to the Config map.
- To update the Anaconda Enterprise server with your changes, restart services by running these commands *on the master node*:

```
sudo gravity enter
kubectl get pods | grep 'workspace\|deploy' | cut -d' ' -f1 | xargs kubectl
↩delete pods
```

To verify that Anaconda Enterprise users can access any NFS volumes you add, stop and restart a project editor session and confirm that the volumes are listed as available directories. See [Loading data](#) for more information.

Addressing NFS downtime


If an NFS server that you have configured as a volume mount in Anaconda Enterprise goes offline, editor sessions, applications and deployment jobs that use it will not start. If NFS downtime occurs, we recommend disabling the mount until the NFS server resumes proper functioning.

To disable an NFS mount:

- Open the Config map and comment out the `volume` section.
- Restart all services as described above.


2.5.8 Disabling sudo for yum

By default, `sudo` access for `yum` is enabled on the Anaconda Enterprise platform. You can easily disable it, however, if your organization requires it.

1. Log in to Anaconda Enterprise, select the **Menu** icon  in the top right corner and click the **Administrative Console** link displayed at the bottom of the slide out window.
2. Click **Manage Resources**.
3. Log in to the Operations Center using the Administrator credentials *configured after installation*.
4. Select **Configuration** from the menu on the left.
5. Verify that the `anaconda-enterprise-anaconda-platform.yml` configuration file is selected in the **Config map** drop-down menu.

Note: We recommend that you make a backup copy of this file since you will be editing it directly.

6. Scroll down to the `sudo-yum` section of the Config map:



7. Change the setting from default to disable:

```
sudo-yum: disable
```

8. Click **Apply** to save your changes.
9. To update the Anaconda Enterprise server with your changes, restart services by running these commands *on the master node*:

```
sudo gravity enter
kubectl get pods | grep ap- | cut -d' ' -f1 | xargs kubectl delete pods
```


To re-enable sudo yum, simply change this Config map setting back to default, save your changes, and restart services.

2.5.9 Specifying alternate wildcard domains

By default, Anaconda Enterprise expects the wildcard domain to be the same for the primary platform server and the application domain.


If your particular implementation uses different domains, you'll need to update the configuration file for the platform with the fully qualified domain name (FQDN) for each server.

Note: Make sure the wildcard domain has a TLS cert and DNS entry that meets [these requirements](#) before you follow the process below to specify it as an `apps-host` or `workspace-host`.


1. Log in to Anaconda Enterprise, select the **Menu** icon  in the top right corner and click the **Administrative Console** link displayed at the bottom of the slide out window.
2. Click **Manage Resources**.
3. Log in to the Operations Center using the Administrator credentials *configured after installation*.
4. Select **Configuration** from the menu on the left.
5. Verify that the `anaconda-enterprise-anaconda-platform.yml` configuration file is selected in the **Config map** drop-down menu.

Note: Any changes you make will impact how Anaconda Enterprise functions, so **we strongly recommend that you save a copy of the original file** before making any changes.

6. Scroll down to the `Deployment server configuration` section of the Config map:




7. Search for and update the `apps-host` setting with the FQDN of the host server you'll be deploying apps to, if it's different than the default Kubernetes server.
8. Scroll down to the `Workspace server configuration` section of the Config map:
9. Update the `workspace-host` setting with the FQDN of the host server you'll be using as a workspace server, if it's different than the default Kubernetes server.
10. Click **Apply** to save your changes.
11. To update the Anaconda Enterprise server with your changes, restart services by running these commands *on the master node*:



```
sudo gravity enter
kubectl get pods | grep ap- | cut -d' ' -f1 | xargs kubectl delete pods
```

2.5.10 Setting global config variables

Anaconda Enterprise provides a secondary config map (named `anaconda-enterprise-env-var-config`) that you can use to configure the platform. Any environment variables that you add to this config map will be available to sessions, deployments and schedules. This is a convenient alternative to using the Anaconda Enterprise CLI, as you can add any variable [supported by conda configuration](#).

1. Log in to Anaconda Enterprise, select the **Menu** icon  in the top right corner and click the **Administrative Console** link displayed at the bottom of the slide out window.
2. Click **Manage Resources**.
3. Log in to the Operations Center using the Administrator credentials *configured after installation*.
4. Select **Configuration** from the menu on the left.
5. Use the **Config map** drop-down menu to select the `anaconda-enterprise-env-var-config.yml` configuration file. The default config map contains a placeholder only: `ENV_VAR_PLACEHOLDER: foo`.
7. To add an environment variable, replace this placeholder with an actual entry. For example, to configure Anaconda Enterprise to *use a proxy for conda packages*, you might add entries that resemble the following:

```
HTTP_PROXY=proxy.url.com:3128
NO_PROXY=anaconda-test.url.com
```

8. Click **Apply** to save your changes.
9. To update Anaconda Enterprise with your changes, restart services by running these commands *on the master node*:

```
sudo gravity enter
kubectl get pods | grep ap- | cut -d' ' -f1 | xargs kubectl delete pods
```

Using Anaconda Enterprise

3.1 Working with projects

Anaconda Enterprise makes it easy for you to create and share interactive data visualizations, live notebooks or machine learning models built using popular libraries such Python, R, Bokeh and Shiny.

AE uses *projects* to encapsulate all of the components necessary to use or run an application: the relevant packages, channels, scripts, notebooks and other related files, environment variables, services and commands, along with a configuration file named `anaconda-project.yml`. For more information, see [Developing a project](#).

Project components are all compressed into a `.tar.bz2`, `.tar.gz` or `.zip` file to make the project portable—so it's easier to store and share with others.

To get you started, Anaconda Enterprise provides several sample projects, including the following:


- Anaconda Distribution for Python 2.7, 3.5 and 3.6
- Minimal Python templates for versions 2.7, 3.5, 3.6, and 3.7
- R notebooks & R Shiny apps
- Matplotlib and HvPlots written in Jupyter Notebooks
- Panel and HoloViz tutorials
- Dashboards for Gapminder data set, oil and gas exploration, NYC taxi data, and attractor equations
- TensorFlow apps for Flask, Tornado and MNIST trained data
- Tutorial on the Intake data catalog package
- Tutorials for database access and time series modeling

You can access them by clicking **Sample Projects** from the **Projects** view. To use a sample project as a starting point, you can copy it to your project list.

To work with a project, click on it or select **View details** from its menu in the list view. Then use the menu on the left as follows:

- Click **Session** to open the project in the default editor. This is Jupyter Notebook, unless you’ve specified a different editor under **Settings**.
- Click **Deployments** to view *deployments* initiated from this project.
- Click **Schedules** to view and *schedule deployments* of the project.
- Click **Runs** to view a list of all project deployments that have run based on a schedule.
- Click **Share** to *share the project* with selected collaborators.
- Click **Audit Trail** to view a list of all actions performed on the project.
- Click **Settings** to change the project name or default editor—Jupyter Notebook—for the project. For example, if you prefer to work with Apache Zeppelin or JupyterLab, choose it as your default editor.

You can also select a resource profile that *meets or exceeds your requirements for the project*, or delete the project. With admin configurations, your projects (sessions/deployments) can now run separately from the master node.



Warning: Deleting a project is irreversible, and therefore can only be done if it is not *shared*.

To make changes to the project files, click **Open session** .

Note: If the system gets overloaded and there are issues copying, opening, or saving changes to a project, the platform will visually notify you by displaying it in red—in addition to generating a text notification. We recommend you check the notifications in the **Audit Trail** for additional information about the error, or delete the project and try again.

To work with the contents offline, you can download  the compressed file and then upload it to work with it within AE.

You can also create new—or upload existing—projects to add them to the server.


To update the project repository with your changes, you *commit your changes to the project*.

Note: To maintain performance, there is a 1GB file size limit for project files you upload. Anaconda Enterprise projects are versioned using Git, so we recommend you commit only text-based files relevant to a project, and keep them under 100MB. Binary files are difficult for version control systems to manage, so we recommend using storage solutions designed for that type of data, and *connecting to those data sources* from within your Anaconda Enterprise sessions.



If your organization would prefer to use its own supported external version control repository, your Administrator can configure Anaconda Enterprise to use that repository instead of the internal GitHub server. After they do so, **you will be prompted for your personal access token before you create your first project** in Anaconda Enterprise. We recommend you create an ever-lasting token, so you can retain permanent access to your files from within Anaconda Enterprise. See *Configuring your user settings* for the permissions that must be set for your auth token, and the steps to configure connectivity to your version control repository.


3.1.1 Editing a project

After you have created your project so that it appears in your **Projects** list, you can open a project session to make changes to the project.



To edit a project:

1. Click the **Open session** icon  to open the project in the editor specified the project.
2. Make your changes to the project, and save them locally. A badge is displayed on the **Commit Changes** icon  to indicate that you've made changes that haven't been committed to the server.



3. When you're ready to update the repository with your changes, click the icon to *commit your changes*. If the project is shared, others will then be able to access your changes, See *collaborating on projects* for important things to consider when working with others on shared projects.

4. When you're done working with the project, click the **Stop session** icon . The session is listed in the **Audit Trail** for the project.

You can also leave a project session open, and click the **Return to session**  when you're ready to resume work.

Tip: See *Developing your project* to learn how to manage the dependencies for your project, so you can run it and deploy it.

3.1.2 Developing a project


To enable Anaconda Enterprise to manage the dependencies for your project—so you can run it and deploy it—you need to configure the following settings for each project you create or upload:

- *Include all the packages used by the project* (e.g., conda, pip, system).
- *Create a custom Conda environment.*
- *Specify the deployment command required to run the project.*
- *Specify environment variables to use in editor sessions and deployments.*


All dependencies are tracked in a project's `anaconda-project.yml` file. While there are various ways to modify this file—using the user interface or a command-line interface—any changes to a project's configuration *will persist for future project sessions and deployments*, regardless of the method you use.

Note: This is different than using `conda install` to add a package using the conda environment during a session, as that method impacts the project temporarily, *during the current session only*.

Jupyter Notebook supports `anaconda-project` commands only. You'll need to run these commands in a terminal. To open a terminal window within a Jupyter Notebook editor session:



If you prefer to use the UI to configure your project settings, you'll need to change the default editor from Jupyter Notebook to JupyterLab. Do this in the project's **Settings** and restart the editor session.



Adding packages to a project

Anaconda Enterprise offers several ways to add packages to a project, so you can choose the method you prefer:

- In a JupyterLab editing session, click the **Project** tab on the far left and click the Edit pencil icon in the **PACKAGES** field. Add your packages and click **Save**.

—OR—

- In a terminal run `anaconda-project add-packages` followed by the package names and optionally the versions.

EXAMPLE: `anaconda-project add-packages hvplot pandas=0.25`

The command may take a moment to run as it collects the dependencies and downloads the packages. The packages will be visible in the project's `anaconda-project.yml` file. If this file is already open, close it and reopen it to see your changes.

To install packages *from a specific channel*:

EXAMPLE: `anaconda-project add-packages -c conda-forge tranquilizer`

Warning: `anaconda-project` commands must be run from the `lab_launch` environment. This is the default environment when using the Jupyter Notebook terminal. For JupyterLab it will be the first terminal on left. If your terminal prompt is not `(lab_launch)` you can activate it with the command `conda activate lab_launch`.

Note: The default `channel_alias` for `conda` in Anaconda Enterprise is configured to point to *the internal package repository*, which means that short channel names will refer to channels in the internal package repository.

To use packages from an external or online package repository, you will need to specify the full channel URL such as `anaconda-project add-packages bokeh -c https://conda.anaconda.org/pyviz` in a command or in `anaconda-project.yml`. The `channel_alias` can be *customized by an administrator*, which affects all sessions and deployments.

If you are working in an air-gapped environment (without internet access), your Administrator will need to *mirror the packages into your organization's internal package repository* for you to be able to access them.

To install pip packages:

List the packages in the `pip:` section of `anaconda-project.yml`. For example:

```
packages:
- six>=1.4.0
- gunicorn==19.1.0
- pip:
  - python-mimeparse
  - falcon==1.0.0
```

After editing the `anaconda-project.yml` file to include the `pip` packages you want to install, run the `anaconda-project prepare` command to install the packages.

To install system packages:

In a terminal, run `sudo yum install` followed by the package name.

EXAMPLE: `sudo yum install sqlite`

Note: Any system packages you install from the command line are available *during the current session only*. If you want them to persist, add them to the project's `anaconda-project.yml` file. **The system package must be available in an Anaconda Enterprise channel** for it to be installed correctly via the `anaconda-project.yml` file.

Custom project environment

Note: Each project only supports the use of a single environment.

For the *standard template projects* the Conda environments have been pre-built as a bootstrap to reduce initialization time when additional packages are added as described above. However, you may wish to create a custom environment specification.

You may use either of these methods to specify the environment for a project:

- In a JupyterLab editing session, click the **Project** tab on the far left and click the plus sign to the right of the **ENVIRONMENTS** field. Choose whether you want to **Prepare all environments** or **Add environments**.

Select an environment and then select **Run**, **Check** or **Edit**. Running an environment opens a terminal window with that environment active.

When creating an environment, you may choose to inherit from an existing environment, and choose the environment's supported platforms, its channels, and its packages.

–or–

- You can use the terminal and command line. For example, to create an environment called `new_env` with `notebook`, `pandas`, and `bokeh`:

```
anaconda-project add-env-spec --name new_env
anaconda-project add-packages --env-spec new_env notebook pandas=0.25 panel=0.6
```

Remove the original environment that corresponds to the template you chose when you initially created the project. For example, to remove the Python 3.6 environment:

```
anaconda-project remove-env-spec anaconda50_py36
```


Warning: For your changes to take effect, you must *commit all changes to the project*, then *stop and re-start the project*.

Note: You must include the `notebook` package for the environment to edit and run notebooks in either the Jupyter Notebook or JupyterLab editors.

Tip: Using the `anaconda-project` command ensures that the environment will prepare correctly when the session is restarted. For more information about `anaconda-project` commands type `anaconda-project --help`.

To verify whether an environment has been initialized for a Notebook session:

1. Within the Notebook session, open a terminal window:



2. Run the following commands to list the contents of the parent directory:

```
jupyter

(lab_launch) pwd
/opt/continuum/project
(lab_launch) cd ..
(lab_launch) ls
anaconda  downloads  prepare.log  scripts
(lab_launch) |
```

If the environment is being initialized, you'll see a file named `preparing`. When the environment has finished initializing, it will be replaced by a file named `prepare.log`.

Tip: If you need to troubleshoot session startup, you can use a terminal to view the session startup logs. When session startup begins, the output of the `anaconda-project prepare` command is written to `/opt/continuum/preparing`, and when the command completes, the log is moved to `/opt/continuum/prepare.log`.

Adding deployment commands to a project

You can use Anaconda Enterprise to deploy projects containing notebooks, Bokeh applications, and generic scripts or web frameworks. Before you can *deploy a project*, it needs to have an appropriate deployment command associated with it.

Each of the following methods can be used to add a deployment command in the project's config file `anaconda-project.yml`:

- In a JupyterLab editing session, click the **Project** tab on the far left and click the plus sign to the right of the **COMMANDS** field. Add information about the command and click **Save**.

Note: This method is available within the JupyterLab editor only, so you'll need to set that as your default editor—in the project's **Settings**—and restart the project session to see this option in the user interface. The two methods described below do not show notifications in the user interface.

–or–

- Use the command line interface:

EXAMPLE: `anaconda-project add-command --type notebook default data-science-notebook.ipynb`

The following are example deployment commands you can use:

For a Notebook:

```
commands:
  default:
    notebook: your-notebook.ipynb
```

For a project with a Bokeh (version 0.12) app defined in a `main.py` file:

```
commands:
  default:
    bokeh_app: .
    supports_http_options: True
```

For a Panel dashboard (panel must be installed in your project):

```
commands:
  default:
    unix: panel serve script-or-notebook-file
    supports_http_options: True
```

For a generic script or web framework, including Python or R:

```
commands:
  default:
    unix: bash run.sh
    supports_http_options: true
```


```
commands:
  default:
    unix: python your-script.py
    supports_http_options: true
```

```
commands:
  default:
    unix: Rscript your-script.R
    supports_http_options: true
```

Note: For deployment commands that can handle `anaconda-project--` arguments (like Panel) `supports_http_options: True` must be added to the command.

To validate your `anaconda-project.yml` and verify your project will deploy successfully:


1. Within the Notebook session, open a terminal window:



2. Run the following command, replacing `anaconda44_py35` with the name of your environment, if it's different:

```
anaconda-project prepare --env-spec anaconda44_py35
```

If the environment includes everything needed to deploy the project, you'll see a message like the following:



Otherwise, any errors preventing a successful deployment will be identified.

If you want to test the deployment immediately after preparing the environment, run the following command instead:

```
anaconda-project run <command-name>
```

If there are any errors preventing a successful deployment, they will be displayed in the terminal.

Environment variables

You can add environment variables that will be set when you run notebooks in an editor session and at the start of a deployment command.

- In a JupyterLab editing session, click the **Project** tab on the far left and click the + button next to **VARIABLES**. Provide the name, description and default value of all variables you require.

—or—

- You can use the terminal and command line. For example, to add an environment variable that sets MY_VAR to hello.:

```
anaconda-project add-variable --default hello MY_VAR
```

3.1.3 Saving and committing changes in a project

Saving changes to files within an editor or project is different from committing those changes to the Anaconda Enterprise server. For example, when you select **File > Save** within an editor, you *save your changes to your local copy of the file* to preserve the work you’ve done.


Warning: Files names containing unicode characters—special characters, punctuation, symbols—can’t be committed to the server, so avoid them when naming files.

When you’re ready to update the server with your changes, you *commit your changes to the project*. This also allows others to access your changes, if the project is shared. See [collaborating on projects](#) for important things to consider when working with others on shared projects.

Note: If the size of your stored git files totals more than 1GB, your system may become bogged down and inoperative. As such, we recommend keeping file sizes under 50MB. If a file of greater size is required for your work, please contact your administrator.

Binary files are difficult for version control systems to manage, so we recommend using storage solutions designed for that type of data, and connecting to those data sources from within your Anaconda Enterprise sessions.

To commit your changes:

1. Click the **Commit Changes** icon. 
2. Select the files you have modified and want to commit. If a file that you changed isn’t displayed in this list, make sure you saved it locally.

Note: Editors create temporary files that may be displayed in the file list. For example, Jupyter Notebook and JupyterLab both create a hidden folder named `.ipynb_checkpoints` for each notebook project you create. This folder is hidden because the editor uses it internally, to capture the state of your `.ipynb` file between auto-save operations. We recommend you [add this and any other hidden folders to your .gitignore file](#), so they are excluded from the list of project files that are checked into version control.

3. Enter a message that briefly describes the changes you made to the files or project. This information is useful for differentiating your commit from others.

4. Enter a meaningful label or version number for your project commit in the **Tag** field. You can use tags to create multiple versions of a single project so that you—or collaborators—can easily deploy a specific version of the project. See [deploying a project](#) for more information.
5. Click **Commit**.

3.1.4 Collaborating on projects

Effective collaboration is key to the success of any enterprise-level project, so it's essential to understand how to work well with others in shared projects.

To give others access to a project that you've created, you can add them as a *collaborator*.

When you add a user (or group of users) as collaborators on a project, it means that they have permission to edit the project *files* and commit changes to the master copy on the server while you may be actively working on a local copy. The only project *setting* they'll be able to change is the default editor—all other project settings will be disabled for editing.


Note: Anaconda Enterprise creates a repository for each project that you create, and will authorize only those users who have been explicitly added as project collaborators to update [the version control repository configured](#) for your organization with their changes to the project.

Anaconda Enterprise tracks all changes to a project and lets you know when files have been updated, so you can choose which version to use.

Sharing a project

You can share a project with specific users or groups of users

1. Click **Projects** to view all of your projects.
2. Click the project you want to share and select **Share** in the left menu.
3. Start typing the name of the user or group in the Add New Collaborator drop-down to search for matches. Select the one that corresponds to what you want and click **Add**.




To unshare—or remove access to—a project, check the large **X** next to the collaborator you want to remove and click **Remove** to confirm your selection.

Note: If you remove a collaborator from a project *while they have a session open for that project*, they might see a 500 Internal Server Error message. To avoid this, ask them to close their running session before you remove them from the project.

Any collaborators you share your project with will see the project in their **Projects** list when they log in to AE, and if others share their projects with you, they'll appear in yours.

Getting updates from other users

When a collaborator makes a change to the project, a badge will appear beside the **Fetch Changes** icon .

Click this icon to pull changes from the server and update your local copy of the project with any changes made by other collaborators.

Anaconda Enterprise compares the copy of the project files you have locally with those on the server and notifies if any files have a conflict. If there is no file conflict, your local copies are updated.

Note: Fetching the latest changes may overwrite or delete your local copy of files without warning if a collaborator has committed changes to the server and you have not made changes to the same files, as there is no file conflict.

EXAMPLE:

- Alice and Bob are both collaborators a project that includes `file1.txt`.
- Alice deletes `file1.txt` from her local copy of the project and commits her changes to the server.
- Bob pulls the latest changes from the server. Bob hasn't edited `file1.txt`, so `file1.txt` is deleted from Bob's local version of the project. Bob's local copy of the project and the version on the server now match exactly.

If the updates on the server conflict with changes you have made locally, you can choose one of the following options:

- **Cancel the Pull.**
- **Keep theirs and Pull**—discards your local changes in favor of theirs. Your changes will be lost.
- **Keep mine and Pull**—discards changes on the server in favor of your local changes. Their changes will be overwritten.
- **Keep both and Pull**—saves the conflicting files with different filenames so you can compare the content of the files and decide how you want to reconcile the differences. See [resolving file conflicts](#) below for more information.

Note: If you have a file open that has been modified by fetching changes, close and reopen the file for the changes to be reflected. Otherwise, the next time you save the file, you may see a “File has been overwritten on disk” alert in JupyterLab. This alert lets you choose whether to cancel the save, discard the current version and open the version of the file on disk, or overwrite the file on disk with the current version.

Committing your changes

After you have saved your changes locally, click the **Commit Changes** icon  to update the master copy on the server with your changes.

If your changes conflict with updates made by other collaborators, a list of the files impacted will be highlighted in red. You may choose how you want to proceed from the following options:

- **Cancel the Commit.**
- **Proceed with the Commit**—overwrites your collaborators' changes. Proceed with caution when choosing this option. Collaborators may not appreciate having their work overwritten, and important work may be lost in the process.
- **Selectively Commit**—commit only those files which don't have conflicts by unchecking the ones highlighted in red.

Committing changes to the server involves a full sync, so any changes that have been made to the project on the server—that do not conflict with your changes—are pulled in the process. This means that after committing your changes, your local copy will match the master copy on the server.

Resolving file conflicts

File conflicts result whenever you have updated a file locally, while a collaborator has changed that same file in their copy of the project and committed their changes to the master copy on the server.

In these cases, you may want to select **Keep both and Pull** to save the conflicting files with different filenames. This enables you to compare the content of the files and decide the best approach to take to reconcile the differences. *The solution will likely involve manually editing the file* to combine both sets of changes and then committing the file.

EXAMPLE: If a file is named `Some Data.txt` and Alice has committed updates to that file on the server, your new local copy of the file from the server—containing Alice's changes—will be named `Some Data.txt (Alice's conflicted file)`. Your local copy named `Some Data.txt` will not change.


3.2 Using project templates

In addition to sample projects, Anaconda Enterprise provides project *templates* to help you get started with configuring and developing in your project. Project templates provide pre-built Conda environments in your project editor session where a number of packages have already been installed.

Templates are provided for common environments such as *Python*, *R*, and *Spark and Hadoop*.

Each template environment includes many of the most popular data science packages. You can use `anaconda-project` commands to *customize them as needed*.

To use one of the available templates, simply select it from the **Environment** list when you create your project:



3.2.1 Python templates

Anaconda Enterprise templates environments are provided Python versions 2.7, 3.5, and 3.6.

In a running project session the Python 2.7 environment includes all of the packages in the [Anaconda distribution for Python 2.7 with a check mark](#) in the **In Installer** column. The same is true for the [Python 3.5](#) and [Python 3.6](#) environments.

Additional Conda and pip packages can be added using the process described in [Developing a project](#).

For example, to upgrade to a newer version of Pandas and add the HvPlot package, run the following in a terminal

```
anaconda-project add-packages pandas=0.25 hvplot
```

Python notebooks can be edited with any of the editors provided with Anaconda Enterprise: Jupyter Notebooks, JupyterLab, or Apache Zeppelin. To change the default editor for your Python project, click on it or select **View details** from its menu in the list view. Then click **Settings** to select your preferred editor. For more information, see [Working with projects](#).

3.2.2 R templates

The R template contains the R Essentials bundle of approximately 80 packages: r-base version 3.4.2, plus the most commonly used R packages for data science, including caret, dplyr, ggplot2, glmnet, irkernel, rbokeh, shiny, and tidyverse.

You can add other R packages as described in [Developing a project](#). You'll need to be able to connect to the appropriate repository to do so. Otherwise, your Administrator may need to [mirror the channels and packages](#) for you to be able to access them.

R notebooks can be edited with any of the editors provided with Anaconda Enterprise: Jupyter Notebooks, JupyterLab, or Apache Zeppelin. To change the default editor for your R project, click on it or select **View details** from

its menu in the list view. Then click **Settings** to select your preferred editor. For more information, see [Working with projects](#).

3.2.3 Hadoop / Spark

If your Anaconda Enterprise Administrator has configured Livy server for Hadoop and Spark access, you'll be able to access them within the platform.

The Hadoop/Spark project template includes sample code to connect to the following resources, with and without [Kerberos authentication](#):

- [Spark](#)
- [Hadoop Distributed File System \(HDFS\)](#)
- [Hive](#)
- [Impala](#)

In the editor session there are two environments created. `anaconda50_hadoop` contains the packages consistent with the Python 3.6 template plus additional packages to access Hadoop and Spark resources. The `anaconda50_impala` environment contains packages consistent with the Python 2.7 template plus additional packages to access Impala tables using the Impyla Python package.

Using Kerberos authentication

If the Hadoop cluster is configured to use Kerberos authentication—and your Administrator has configured Anaconda Enterprise to work with Kerberos—you can use it to authenticate yourself and gain access to system resources. The process is the same for all services and languages: Spark, HDFS, Hive, and Impala.

Note: You'll need to contact your Administrator to get your Kerberos *principal*, which is the combination of your username and security domain.

To perform the authentication, open an environment-based terminal in the interface. This is normally in the Launchers panel, in the bottom row of icons, and is the right-most icon.

When the interface appears, run this command:

```
kinit myname@mydomain.com
```

Replace `myname@mydomain.com` with the Kerberos *principal*, the combination of your username and security domain, which was provided to you by your Administrator.

Executing the command requires you to enter a password. If there is no error message, authentication has succeeded. You can verify by issuing the `klist` command. If it responds with some entries, you are authenticated.

You can also use a keytab to do this. Upload it to a project and execute a command like this:

```
kinit myname@mydomain.com -kt mykeytab.keytab
```

Note: Kerberos authentication will lapse after some time, requiring you to repeat the above process. The length of time is determined by your cluster security administration, and on many clusters is set to 24 hours.

For deployments that require Kerberos authentication, we recommend generating a shared Kerberos keytab that has access to the resources needed by the deployment, and adding a `kinit` command that uses the keytab as part of the deployment command.

Alternatively, the deployment can include a form that asks for user credentials and executes the `kinit` command.

Using Spark

Apache Spark is an open source analytics engine that runs on compute clusters to provide in-memory operations, data parallelism, fault tolerance, and very high performance. Spark is a general purpose engine and highly effective for many uses, including ETL, batch, streaming, real-time, big data, data science, and machine learning workloads.

Note: Using Anaconda Enterprise with Spark requires Livy and Sparkmagic. The Hadoop/Spark project template includes Sparkmagic, but your Administrator must have configured Anaconda Enterprise to work with a Livy server.

Supported versions

The following combinations of the multiple tools are supported:


- Python 2 and Python 3, Apache Livy 0.5, Apache Spark 2.1, Oracle Java 1.8
- Python 2, Apache Livy 0.5, Apache Spark 1.6, Oracle Java 1.8

Livy

Apache Livy is an open source REST interface to submit and manage jobs on a Spark cluster, including code written in Java, Scala, Python, and R. These jobs are managed in Spark contexts, and the Spark contexts are controlled by a resource manager such as Apache Hadoop YARN. This provides fault tolerance and high reliability as multiple users interact with a Spark cluster concurrently.

With Anaconda Enterprise, you can connect to a remote Spark cluster using Apache Livy with any of the available clients, including Jupyter notebooks with Sparkmagic. Anaconda Enterprise provides Sparkmagic, which includes Spark, PySpark, and SparkR notebook kernels for deployment.

The Apache Livy architecture gives you the ability to submit jobs from any remote machine or analytics cluster, even where a Spark client is not available. It removes the requirement to install Jupyter and Anaconda directly on an edge node in the Spark cluster.



Livy and Sparkmagic work as a REST server and client that:

- Retains the interactivity and multi-language support of Spark
- Does not require any code changes to existing Spark jobs
- Maintains all of Spark’s features such as the sharing of cached RDDs and Spark Dataframes, and
- Provides an easy way of creating a secure connection to a Kerberized Spark cluster.

When Livy is installed, you can connect to a remote Spark cluster when creating a new project by selecting the Spark template.

Kernels

When you copy the project template “Hadoop/Spark” and open a Jupyter editing session, you will see several kernels such as these available:

- Python 3
- PySpark
- PySpark3
- Python 3
- R
- Spark
- SparkR
- Python 2

To work with Livy and Python, use `PySpark`. Do not use `PySpark3`.

To work with Livy and R, use R with the `sparklyr` package. Do not use the kernel `SparkR`.

To work with Livy and Scala, use `Spark`.

You can use Spark with Anaconda Enterprise in two ways:

1. Starting a notebook with one of the Spark kernels, in which case all code will be executed on the cluster and not locally.

Note that a connection and all cluster resources will be assigned as soon as you execute any ordinary code cell, that is, any cell not marked as `%%local`.

2. Starting a normal notebook with a Python kernel, and using `%load_ext sparkmagic.magics`. That command will enable a set of functions to run code on the cluster. See [examples](#) (external link).

To display graphical output directly from the cluster, you must use SQL commands. This is also the only way to have results passed back to your local Python kernel, so that you can do further manipulation on it with `pandas` or other packages.

In the common case, the configuration provided for you in the Session will be correct and not require modification. However, in other cases you may need to use sandbox or ad-hoc environments that require the modifications described below.

Overriding session settings

Certain jobs may require more cores or memory, or custom environment variables such as Python worker settings. The configuration passed to Livy is generally defined in the file `~/.sparkmagic/conf.json`.

You may inspect this file, particularly the section `"session_configs"`, or you may refer to the example file in the `spark` directory, `sparkmagic_conf.example.json`. Note that the example file has not been tailored to your specific cluster.

In a Sparkmagic kernel such as `PySpark`, `SparkR`, or similar, you can change the configuration with the magic `%%configure`. This syntax is pure JSON, and the values are passed directly to the driver application.

EXAMPLE:

```
%%configure -f
{"executorMemory": "4G", "executorCores": 4}
```

To use a different environment, use the Spark configuration to set `spark.driver.python` and `spark.executor.python` on all compute nodes in your Spark cluster.

EXAMPLE:

If all nodes in your Spark cluster have Python 2 deployed at `/opt/anaconda2` and Python 3 deployed at `/opt/anaconda3`, then you can select Python 2 on all execution nodes with this code:

```
%%configure -f
{"conf": {"spark.driver.python": "/opt/anaconda2/bin/python", "spark.executor.python":
↪": "/opt/anaconda2/bin/python"}}
```

If all nodes in your Spark cluster have Python 2 deployed at `/opt/anaconda2` and Python 3 deployed at `/opt/anaconda3`, then you can select Python 3 on all execution nodes with this code:

```
%%configure -f
{"conf": {"spark.driver.python": "/opt/anaconda3/bin/python", "spark.executor.python":
↪": "/opt/anaconda3/bin/python"}}
```

If you are using a Python kernel and have done `%load_ext sparkmagic.magics`, you can use the `%manage_spark` command to set configuration options. The session options are in the “Create Session” pane under “Properties”.

Overriding session settings can be used to target multiple Python and R interpreters, including Python and R interpreters coming from different Anaconda parcels.

Using custom Anaconda parcels and management packs

Anaconda Enterprise Administrators can generate custom parcels for Cloudera CDH or custom management packs for Hortonworks HDP to distribute customized versions of Anaconda across a Hadoop/Spark cluster using Cloudera Manager for CDH or Apache Ambari for HDP. See [Using installers, parcels and management packs](#) for more information.

As a platform user, you can then select a specific version of Anaconda and Python on a per-project basis by including the following configuration in the first cell of a Sparkmagic-based Jupyter Notebook.

For example:

```
%%configure -f
{"conf": {"spark.yarn.appMasterEnv.PYSPARK_PYTHON": "/opt/anaconda/bin/python",
          "spark.yarn.appMasterEnv.PYSPARK_DRIVER_PYTHON": "/opt/anaconda/bin/python",
          "spark.yarn.executorEnv.PYSPARK_PYTHON": "/opt/anaconda/bin/python",
          "spark.pyspark.python": "/opt/anaconda/bin/python",
          "spark.pyspark.driver.python": "/opt/anaconda/bin/python"
        }
}
```

Note: Replace `/opt/anaconda/` with the prefix of the name and location for the particular parcel or management pack.

Overriding basic settings

In some more experimental situations, you may want to change the Kerberos or Livy connection settings. This could be done when first configuring the platform for a cluster, usually by an administrator with intimate knowledge of the cluster’s security model.

Users could override basic settings if their administrators have not configured Livy, or to connect to a cluster other than the default cluster.

```

In [1]: %configure -f
{
  "conf": {
    "spark.yarn.appMasterEnv.PYSPARK_PYTHON": "/opt/anaconda/bin/python",
    "spark.yarn.appMasterEnv.PYSPARK_DRIVER_PYTHON": "/opt/anaconda/bin/python",
    "spark.yarn.executorEnv.PYSPARK_PYTHON": "/opt/anaconda/bin/python",
    "spark.pySpark.python": "/opt/anaconda/bin/python",
    "spark.pySpark.driver.python": "/opt/anaconda/bin/python"
  }
}

Current session config: {'conf': {'spark.yarn.appMasterEnv.PYSPARK_PYTHON': '/opt/anaconda/bin/python',
'spark.yarn.appMasterEnv.PYSPARK_DRIVER_PYTHON': '/opt/anaconda/bin/python', 'spark.yarn.executorEnv.PYSPARK_PYTHON':
'/opt/anaconda/bin/python', 'spark.pySpark.python': '/opt/anaconda/bin/python', 'spark.pySpark.driver.python':
'/opt/anaconda/bin/python'}, 'kind': 'pySpark'}

No active sessions.

In [2]: %info

Current session config: {'conf': {'spark.yarn.appMasterEnv.PYSPARK_PYTHON': '/opt/anaconda/bin/python',
'spark.yarn.appMasterEnv.PYSPARK_DRIVER_PYTHON': '/opt/anaconda/bin/python', 'spark.yarn.executorEnv.PYSPARK_PYTHON':
'/opt/anaconda/bin/python', 'spark.pySpark.python': '/opt/anaconda/bin/python', 'spark.pySpark.driver.python':
'/opt/anaconda/bin/python'}, 'kind': 'pySpark'}

No active sessions.

In [3]: %l

Starting Spark application


| ID | YARN Application ID          | Kind    | State | Spark UI           | Driver log          | Current session? |
|----|------------------------------|---------|-------|--------------------|---------------------|------------------|
| 0  | application_151378486453_004 | pySpark | idle  | <a href="#">UI</a> | <a href="#">Log</a> | ✓                |


SparkContext available as 'sc'.
SqlContext available as 'sqlContext'.
2

```

In these cases, we recommend creating a `krb5.conf` file and a `sparkmagic_conf.json` file in the project directory so they will be saved along with the project itself. An example Sparkmagic configuration is included, `sparkmagic_conf.example.json`, listing the fields that are typically set. The `"url"` and `"auth"` keys in each of the kernel sections are especially important.

The `krb5.conf` file is normally copied from the Hadoop cluster, rather than written manually, and may refer to additional configuration or certificate files. These files must all be uploaded using the interface.

To use these alternate configuration files, set the `KRB5_CONFIG` variable default to point to the full path of `krb5.conf` and set the values of `SPARKMAGIC_CONF_DIR` and `SPARKMAGIC_CONF_FILE` to point to the Sparkmagic config file. You can set these either by using the Project pane on the left of the interface, or by directly editing the `anaconda-project.yml` file.

For example, the final file's variables section may look like this:

```

variables:
  KRB5_CONFIG:
    description: Location of config file for kerberos authentication
    default: /opt/continuum/project/krb5.conf
  SPARKMAGIC_CONF_DIR:
    description: Location of sparkmagic configuration file
    default: /opt/continuum/project
  SPARKMAGIC_CONF_FILE:
    description: Name of sparkmagic configuration file
    default: sparkmagic_conf.json

```

Note: You must perform these actions **before** running `kinit` or starting any notebook/kernel.

Warning: If you misconfigure a `.json` file, all Sparkmagic kernels will fail to launch. You can test your Sparkmagic configuration by running the following Python command in an interactive shell: `python -m json.tool sparkmagic_conf.json`.

If you have formatted the JSON correctly, this command will run without error. Additional edits may be required, depending on your Livy settings. See [Installing Livy server for Hadoop Spark access](#) and [Configuring Livy server for Hadoop Spark access](#) for information on installing and configuring Livy.

Python

Example code showing Python with a Spark kernel:

```
sc

data = sc.parallelize(range(1, 100))

data.mean()

import pandas as pd

df = pd.DataFrame([("foo", 1), ("bar", 2)], columns=["col1", "col2"])

sparkdf = sqlContext.createDataFrame(df)

sparkdf.select("col1").show()

sparkdf.filter(sparkdf['col2'] == 2).show()
```

Using HDFS

The Hadoop Distributed File System (HDFS) is an open source, distributed, scalable, and fault tolerant Java based file system for storing large volumes of data on the disks of many computers. It works with batch, interactive, and real-time workloads.

Dependencies

- python-hdfs

Supported versions

- Hadoop 2.6.0, Python 2 or 3

Kernels

- [anaconda50_hadoop] Python 3

Connecting

To connect to an HDFS cluster you need the address and port to the HDFS Namenode, normally port 50070.

To use the `hdfscli` command line, configure the `~/hdfscli.cfg` file:

```
[global]
default.alias = dev

[dev.alias]
url = http://<Namenode>:port
```

Once the library is configured, you can use it to perform actions on HDFS with the command line by starting a terminal based on the [anaconda50_hadoop] Python 3 environment and executing the `hdfscli` command. For example:

```
$ hdfscli

Welcome to the interactive HDFS python shell.
The HDFS client is available as `CLIENT`.

In [1]: CLIENT.list("/")
Out[1]: ['hbase', 'solr', 'tmp', 'user']
```

Python

Sample code showing Python with HDFS without Kerberos:

```
from hdfs import InsecureClient

client = InsecureClient('http://<Namenode>:50070')
client.list("/")
```

Python with HDFS with Kerberos:

```
from hdfs.ext.kerberos import KerberosClient

client = KerberosClient('http://<Namenode>:50070')
client = KerberosClient('http://ip-172-31-14-99.ec2.internal:50070')
client.list("/")
```

Using Hive

Hive is an open source data warehouse project for queries and data analysis. It provides an SQL-like interface called HiveQL to access distributed data stored in various databases and file systems.

Hive is very flexible in its connection methods and there are multiple ways to connect to it, such as JDBC, ODBC and Thrift. Anaconda recommends Thrift with Python and JDBC with R.

Dependencies

- pyhive
- RJDBC

Supported versions

- Hive 1.1.0, JDK 1.8, Python 2 or Python 3

Kernels

- [anaconda50_hadoop] Python 3

Drivers

Using JDBC requires downloading a driver for the specific version of Hive that you are using. This driver is also specific to the vendor you are using.

Cloudera EXAMPLE:

- [Hive JDBC Connector 2.5.4 - Download](#)
- [Hive JDBC Connection 2.5.4 - Documentation](#)

We recommend downloading the respective JDBC drivers and committing them to the project so that they are always available when the project starts.

Once the drivers are located in the project, Anaconda recommends using the [RJDBC](#) library to connect to Hive. Sample code for this is shown below.

Connecting

To connect to a Hive cluster you need the address and port to a running Hive Server 2, normally port 10000.

To use PyHive, open a Python notebook based on the [anaconda50_hadoop] Python 3 environment and run:

```
from pyhive import hive
conn = hive.connect('<Hive Server 2>', port=10000)
cursor = conn.cursor()
cursor.execute('SHOW DATABASES')
cursor.fetchall()
```

Python

Anaconda recommends the Thrift method to connect to Hive from Python. With Thrift you can use all the functionality of Hive, including security features such as SSL connectivity and Kerberos authentication. Thrift does not require special drivers, which improves code portability.

Instead of using an ODBC driver for connecting to the SQL engines, a Thrift client uses its own protocol based on a service definition to communicate with a Thrift server. This definition can be used to generate libraries in any language, including Python.

Hive using PyHive:

```
from pyhive import hive

conn = hive.connect('<Hive Server 2>', port=10000, auth='KERBEROS', kerberos_service_
↪name='hive')
```

(continues on next page)

(continued from previous page)

```
cursor.execute('SHOW TABLES')
cursor.fetchall()

# This prints: [('iris',), ('t1',)]

cursor.execute('SELECT * FROM iris')
cursor.fetchall()

# This prints the output of that table
```

Note: The output will be different, depending on the tables available on the cluster.

R

Anaconda recommends the JDBC method to connect to Hive from R.

Using JDBC allows for multiple types of authentication including Kerberos. The only difference between the types is that different flags are passed to the URI connection string on JDBC. Please follow the official documentation of the driver you picked and for the authentication you have in place.

Hive using RJDBC:

```
library("RJDBC")

hive_classpath <- list.files("<PATH TO JDBC DRIVER>", pattern="jar$", full.names=T)

drv <- JDBC(driverClass = "com.cloudera.hive.jdbc4.HS2Driver", classPath = hive_
  ↳classpath, identifier.quote="'")

url <- "jdbc:hive2://<HIVE SERVER 2 HOST>:10000/default;SSL=1;AuthMech=1;KrbRealm=
  ↳<KRB REALM>;KrbHostFQDN=<KRB HOST>;KrbServiceName=hive"

conn <- dbConnect(drv, url)

dbGetQuery(conn, "SHOW TABLES")

dbDisconnect(conn)
```

Note: The output will be different, depending on the tables available on the cluster.

Using Impala

Apache Impala is an open source, native analytic SQL query engine for Apache Hadoop. It uses massively parallel processing (MPP) for high performance, and works with commonly used big data formats such as Apache Parquet.

Impala is very flexible in its connection methods and there are multiple ways to connect to it, such as JDBC, ODBC and Thrift. Anaconda recommends Thrift with Python and JDBC with R.

Dependencies

- `impyla`
- `implyr`
- `RJDBC`

Supported versions

- Impala 2.12.0, JDK 1.8, Python 2 or Python 3

Kernels

- Python 2

Drivers

Using JDBC requires downloading a driver for the specific version of Impala that you are using. This driver is also specific to the vendor you are using.

Cloudera EXAMPLE:

- [Impala JDBC Connection 2.5.43 - Download](#)
- [Impala JDBC Connection 2.5.43 - Documentation](#)

We recommend downloading the respective JDBC drivers and committing them to the project so that they are always available when the project starts.

Once the drivers are located in the project, Anaconda recommends using the `RJDBC` library to connect to both Hive and Impala. Sample code for this is shown below.

Connecting

To connect to an Impala cluster you need the address and port to a running Impala Daemon, normally port 21050.

To use Impyla, open a Python Notebook based on the Python 2 environment and run:

```
from impala.dbapi import connect
conn = connect('<Impala Daemon>', port=21050)
cursor = conn.cursor()
cursor.execute('SHOW DATABASES')
cursor.fetchall()
```

Python

Anaconda recommends the Thrift method to connect to Impala from Python. With Thrift you can use all the functionality of Impala, including security features such as SSL connectivity and Kerberos authentication. Thrift does not require special drivers, which improves code portability.

Instead of using an ODBC driver for connecting to the SQL engines, a Thrift client uses its own protocol based on a service definition to communicate with a Thrift server. This definition can be used to generate libraries in any language, including Python.

Impala using Impyla:

```
from impala.dbapi import connect
conn = connect(host='<Impala Daemon>', port=21050, auth_mechanism='GSSAPI', kerberos_
↳service_name='impala')

cursor = conn.cursor()
cursor.execute('SHOW TABLES')

results = cursor.fetchall()
results

# This prints: [('iris',),]

cursor.execute('SELECT * FROM iris')
cursor.fetchall()

# This prints the output of that table
```

Note: The output will be different, depending on the tables available on the cluster.

R

Anaconda recommends the JDBC method to connect to Impala from R.

Using JDBC allows for multiple types of authentication including Kerberos. The only difference between the types is that different flags are passed to the URI connection string on JDBC. Please follow the official documentation of the driver you picked and for the authentication you have in place.

Anaconda recommends **Implyr** to manipulate tables from Impala. This library provides a dplyr interface for Impala tables that is familiar to R users. Implyr uses RJBDC for connection.

Impala using RJBDC and Implyr:

```
library(implyr)
library(RJDBC)

impala_classpath <- list.files(path = "<PATH TO JDBC DRIVER>", pattern = "\\\\.jar$",
↳full.names = TRUE)

drv <- JDBC(driverClass = "com.cloudera.hive.jdbc4.HS2Driver", classPath = hive_
↳classpath, identifier.quote="'")

url <- "jdbc:impala://<IMPALA DAEMON HOST>:10000/default;SSL=1;AuthMech=1;KrbRealm=
↳<KRB REALM>;KrbHostFQDN=<KRB HOST>;KrbServiceName=impala"

# Use implyr to create a dplyr interface

impala <- src_impala(drv, url)

# This will show all the available tables
```

(continues on next page)

(continued from previous page)

```
src_tbls (impala)
```

Note: The output will be different, depending on the tables available on the cluster.

3.3 Working with packages

Anaconda Enterprise uses *packages* to bundle software files and information about the software—such as its name, specific version and description—into a single file that can be easily installed and managed.

Packages are distributed via *channels*. Channels may point to a cloud-based repository or a private location on a remote or local repository that you or someone else in your organization created. For more information, see [Configuring channels and packages](#).

Note: Anaconda Enterprise supports the use of both `conda` and `pip` packages in its repository. To create and share channels and packages from your Anaconda Repository using `conda` commands, first [install `anaconda-enterprise-cli`](#) and log in to your AE instance.

Creating a package requires familiarity with the `conda` package manager and command line interface (CLI), so not all AE users will create packages and channels.

Many Anaconda Enterprise users may interact with packages primarily within the context of *projects* and *deployments*. In this case, they will likely do the following:

- Access and download any packages and installers they need from the list of those available under **Channels**.
- Work with the contents of the package as they create models and dashboards, then
- *Add any packages the project depends on* to the project before *deploying it*.

Other users may primarily *build packages*, *upload them to channels* and *share them with others* to access and download.

3.3.1 Building a conda package

You can build a `conda` package to bundle software files and information about the software—such as its name, specific version and description—into a single file that can be easily installed and managed.

Building a `conda` package requires [installing `conda build`](#) and creating a [conda build recipe](#). You then use the `conda build` command to build the `conda` package from the `conda` recipe.

Tip: If you are new to building packages with `conda`, here are some video tutorials that you may find helpful:

- **Production-grade Packaging with Anaconda | AnacondaCon 2018** This 41-minute presentation by Mahmoud Hashemi covers using conda and conda environments to build an OS package (RPM) and Docker images.
- **The Sheer Joy of Packaging | SciPy 2018 Tutorial** This 210-minute presentation by Michael Sarahan, Filipe Fernandes, Chris Barker, Matt Craig, Matt McCormick, Jean-Christophe Fillion-Robin, Jonathan Helmus, and Ray Donnelly provides end-to-end examples of packaging with PyPI and conda. You can find materials from the tutorial [here](#).
- **Making packages and packaging “just work” | PyData 2017 Tutorial** This 40-minute presentation by Michael Sarahan walks you through critical topics such as the anatomy of a Python package, tools available to make packaging easier, plus how to automate builds and why you might want to do so.

You can build conda packages from a variety of source code projects, most notably Python. For help packaging a Python project, see the [Setuptools documentation](#).

Note: Setuptools is a package development process library designed to facilitate packaging Python projects, and is not part of Anaconda, Inc. Conda-build uses the build system that’s native to the language, so in the case of Python that’s `setuptools`.

After you build the package, you can *upload it to a channel* for others to access.

3.3.2 Uploading a conda package

After you *build a conda package*, you can upload it to a *channel* to make it available for others to use.

A channel is a specific location for storing packages, and may point to a cloud-based repository or a private location on a remote or local repository that you or your organization created. See [Accessing remote package repositories](#) for more information.

Note: There is a 1GB file size limit for package files you upload.

To add a package to an existing channel:

1. Click **Channels** in the top menu to display your existing channels.
2. Select the specific channel you want to add your package to—information about any packages already in the channel is displayed.
3. Click **Upload**, browse for the package and click **Upload**. The package is added to the list.

Now you can *share the channel and packages* with others.

To create a new channel to add packages to:

1. Click **Create** in the upper right corner, enter a meaningful name for the channel and click **Create**.

Note: Channels are `Public`—accessible by non-authenticated users—by default. To make the channel `Private`, and therefore available to authenticated users only, disable the toggle to switch the channel setting from `Public` to `Private`.

2. Click **Upload** to add your package(s) to the channel.

Using the CLI:

You can also create a channel by running the following in a terminal window:

```
anaconda-enterprise-cli channels create <channelname>
```


Note: The channel name <channelname> you enter must not already exist.

Now you can upload a package to the channel by entering the following:

```
anaconda-enterprise-cli upload path/to/pkg/notebookname.tar.bz2 --channel  
-><channelname>
```

Replacing `path/to/pkg/notebookname.tar.bz2` with the actual path to the package you want to upload, and <channelname> with the actual channel name.

To remove a package from a channel, select **Delete** from the command menu for the package:



Note: If the **Delete** command is not available, you don't have permission to remove the package from the channel.

Setting a default channel

There is no `default_channel` in a fresh install, so you'll have to enter a specific channel each time.

If you don't want to enter the `--channel` option with each command, you can set a default channel:

```
anaconda-enterprise-cli config set default_channel <channelname>
```

To display your current default channel:

```
$ anaconda-enterprise-cli config get default_channel  
'<channelname>'
```

After setting the default channel, upload to your default channel:


```
anaconda-enterprise-cli upload <path/to/pkgs/packageName.tar.bz2>
```

Replacing `<path/to/pkgs/packageName.tar.bz2>` with the actual path to the package you want to upload.

3.3.3 Sharing channels and packages

After you *build a package* and *upload it* to a channel, you can enable others to access it by *sharing the channel* with them. You can share a channel with specific users, or groups of users.

To share multiple packages with the same set of users, you can upload all of the packages to a channel and share that channel. This enables you to create channels for each type of user you support, and add the packages they need to each.



The screenshot shows the Anaconda Enterprise web interface. On the left is a dark blue sidebar with navigation links: Projects, Deployments, and Channels (which is highlighted). The main content area has a dark blue header with the Anaconda logo, a search icon, and a 'Create +' button. Below the header is a table with three columns: Channel, Owner, and Last Updated. The table lists several channels, including 'Anaconda', 'anaconda', 'anaconda-enterprise', 'crystal', 'demo2', and 'demo_channel', each with its owner and the last update time. A vertical ellipsis menu is visible at the end of each row.


Channel	Owner	Last Updated
Anaconda	whita	August 5, 2019, 3:15 PM
anaconda	saundramonroe	August 5, 2019, 3:22 PM
anaconda-enterprise	anaconda-enterprise	August 23, 2019, 2:57 PM
crystal	csoja	August 27, 2019, 10:28 AM
demo2	cgunn	August 5, 2019, 10:28 AM
demo_channel	cgunn	August 5, 2019, 10:29 AM

Anyone you share the channel with will see it in their **Channels** list when they log in to Anaconda Enterprise. They can then download the packages in the channel they want to work with, and *add any packages their project depends on* to their project before *deploying it*.

Note: The default is to grant collaborators *read-write* access, so if you want to prevent them from adding and removing packages from the channel, be sure they have *read-only* access. You'll need to *use the CLI* to make a channel read-only.

To share a channel with unauthenticated users:

1. Select the channel in the **Channels** list, and verify that the packages in the channel are all appropriate to share.
2. Click **Share** in the left menu.
3. Ensure the channel is set to `Public`, copy the URL location of the channel, and distribute it to the people with whom you want to share the channel.


**To share a channel with other platform users:**

1. Select the channel in the **Channels** list and verify that all the packages you want to share are listed.
2. Click **Share** in the left menu.

Note: Channels are `Public`—accessible by non-authenticated users—by default. To make the channel `Private`, and therefore available to authenticated users only, disable the toggle to switch the channel setting from `Public` to `Private`.

3. Start typing the name of the user or group in the **Add New Collaborator** drop-down to search for matches. Select the option that corresponds to what you want. You can add multiple users or groups at the same time.
4. Click **Add** when you're satisfied with your selections.

To “unshare” a channel with a collaborator, simply click the large **X** next to the right of their name in the **Collaborator** list.



Using the CLI:

Get a list of all the channels on the platform with the `channels list` command:

```
anaconda-enterprise-cli channels list
```

Share a channel with a specific user using the `share` command:

```
anaconda-enterprise-cli channels share --user username --level r <channelname>
```

You can also share a channel with an existing group created by your Administrator:

```
anaconda-enterprise-cli channels share --group GROUPNAME --level r <channelname>
```

Replacing `GROUPNAME` with the actual name of your group.

Note: Adding `--level r` grants this group read-only access to the channel.

You can “unshare” a channel using the following command:

```
anaconda-enterprise-cli channels share --user <username> --remove <channelname>
```

Run `anaconda-enterprise-cli channels --help` to see more information about what you can do with channels.

For help with a specific command, enter that command followed by `--help`:

```
anaconda-enterprise-cli channels share --help
```

3.3.4 Configuring conda

If you are familiar with conda and want to use it to install the packages you need, you can configure conda to search a specific set of channels for packages. Listing channel locations in the `.condarc` file overrides conda defaults, causing conda to search only the channels listed, in the order specified.

The channels you specify can be *public* or *private*. Private channels will require you to authenticate before you can `conda install` packages from them.

If your organization has configured `conda` *at the system level* to limit platform users to only access packages in your on-premises repository, **this will override your user-level configuration file**.

To configure `conda`, create or update your `~/.condarc` configuration file in the root directory of your local machine to include your preferred repository channels. For example:


```
channels:
- <anaconda_dot_org_username>
- http://some.custom/channel
- file:///some/local/directory
- defaults
```

For more information, see [this section](#) of the `conda` docs.

3.4 Using installers, parcels and management packs

In addition to Anaconda and Miniconda installers, your Administrator may create custom installers, Cloudera Manager parcels, or Hortonworks Data Manager management packs for you and your colleagues to use. They make these specific packages and their dependencies available to you via *channels*.

To view the installers available to you, select the top **Channels** menu, then click the **Installers** link in the top right corner.



Name	Type	Size	Last Modified
test-None-Linux-x86_64.sh https://use12-sp2-test-qademo.devic.com/repository/api/installers/files/6e7ed33e1e844eb645d501fe494c4	conda	41.16 MB	Jul 19, 2018
ABC-Q1.0-Linux-x86_64.sh https://use12-sp2-test-qademo.devic.com/repository/api/installers/files/6cc715b8ea724a0d8cfd125437bb	conda	40.91 MB	Jul 19, 2018
ABC-None-Linux-x86_64.sh https://use12-sp2-test-qademo.devic.com/repository/api/installers/files/4b6bde90455248a88ba0c6c2a673c56	conda	40.91 MB	Jul 19, 2018

To download an installer, simply click on its name in the list.

Note: If you don't see an installer that you expected to see, please contact your Administrator and ask them to *generate the installer* you need.

3.5 Working with data

3.5.1 Loading data into your project

Anaconda Enterprise uses *projects* to encapsulate all of the components necessary to use or run an application: the relevant packages, channels, scripts, notebooks and other related files, environment variables, services and commands, along with a configuration file named `anaconda-project.yml`.

You can also access and load data in a variety of formats, stored in common sources including the following:

- *File systems*
- *NFS shared drives*
- *Databases*
- *Hadoop and Spark clusters*
- Distributed *version control repositories* such as Git and Bitbucket (if configured by your Administrator).

The amount of data you read into your project will impact the resources required to successfully run the project, whether in a notebook session or deployment. See the following section on *understanding resource profiles* to learn more.

Understanding resource profiles

Resource profiles are used to limit the amount of CPU cores and RAM available for use when running a project session or *deployment*.

Note: Choosing a resource profile with a greater number of available cores is not guaranteed to improve performance—it will also depend on whether the libraries used by the project can take advantage of multiple cores, for example.

Memory limits are enforced by the Linux kernel, so when the memory limit is exceeded the most recent process will crash. Be sure to select a resource profile that offers sufficient runtime resources required by your project to avoid such errors. A best practice recommendation is to **choose a resource profile with roughly double the amount of memory required by the size of data you need to read**.

To see the total memory in use, open a terminal and run the following command:

```
cat /sys/fs/cgroup/memory/memory.usage_in_bytes | awk '{print $1/1024/1024}'
```

Uploading files to a project

Open an editing session for the project, then choose the file you want to upload. The process of uploading files varies slightly, based on the editor used:

- In Jupyter Notebook, click **Upload** and select the file to upload. Then click the blue **Upload** button displayed in the file's row to add the file to the project
- In JupyterLab, click the Upload files icon and select the file. In the top right corner, click Commit Changes to add the file to your project.
- In Zeppelin, use the **Import note** feature to select a JSON file or add data from a URL.

Once a file is in the project, you can use code to read it. For example, to load the iris dataset from a comma separated value (CSV) file into a pandas DataFrame:

```
import pandas as pd
irisdf = pd.read_csv('iris.csv')
```

Accessing NFS shared drives

After your Administrator has *configured Anaconda Enterprise to mount an NFS share*, you'll be able to access it from within your notebooks. You'll just need to know the name of the volume, so you can access it. For example, if they named the configuration file section `myvolume`, the share will be mounted at `/data/myvolume`.

From a notebook you can use code such as this to read data from the share:

```
import pandas as pd
irisdf = pd.read_csv('/data/myvolume/iris.csv')
```

Accessing data stored in databases

You can also connect to the following database engines to access data stored within them:

- Cassandra
- Cockroach
- Cosmos
- Couchbase
- Db2
- Elasticsearch
- MariaDB
- MLDB
- MongoDB
- MS SQL
- MySQL
- Neo4j
- Oracle
- PostgreSQL
- Redis
- S3
- Snowflake
- Vertica

See *Storing secrets* for information about adding credentials to the platform, to make them available in your projects. Any secrets you add will be available across all sessions and deployments associated with your user account.

Hadoop Distributed File System (HDFS), Spark, Hive, and Impala

Loading data from HDFS, Spark, Hive, and Impala is discussed in *Hadoop / Spark*.

3.5.2 Exploring project data

With Anaconda Enterprise, you can explore project data using visualization libraries such as Bokeh and Matplotlib, and numeric libraries such as NumPy, SciPy, and Pandas.

Use these tools to discover patterns and relationships in your datasets, and develop approaches for your analysis and deployment pipelines.

The following examples use the [Iris flower data set](#), and this mini customer data set (`customers.csv`):

```
customer_id,title,industry
1,data scientist,retail
2,data scientist,academia
3,compiler optimizer,academia
4,data scientist,finance
5,compiler optimizer,academia
6,data scientist,academia
7,compiler optimizer,academia
8,data scientist,retail
9,compiler optimizer,finance
```

1. Begin by importing libraries, and reading data into a Pandas DataFrame:

```
import pandas as pd
import numpy as np
import matplotlib.pyplot as plt
irisdf = pd.read_csv('iris.csv')
customerdf = pd.read_csv('customers.csv')

%matplotlib inline
```

2. Then list column / variable names:

```
print(irisdf.columns)
```

```
Index(['sepal_length', 'sepal_width', 'petal_length', 'petal_width', 'class'], dtype=
↪ 'object')
```

3. Summary statistics include minimum, maximum, mean, median, percentiles, and more:

```
print('length:', len(irisdf)) # length of data set
print('shape:', irisdf.shape) # length and width of data set
print('size:', irisdf.size) # length * width
print('min:', irisdf['sepal_width'].min())
print('max:', irisdf['sepal_width'].max())
print('mean:', irisdf['sepal_width'].mean())
print('median:', irisdf['sepal_width'].median())
print('50th percentile:', irisdf['sepal_width'].quantile(0.5)) # 50th percentile,
↪ also known as median
print('5th percentile:', irisdf['sepal_width'].quantile(0.05))
print('10th percentile:', irisdf['sepal_width'].quantile(0.1))
print('95th percentile:', irisdf['sepal_width'].quantile(0.95))
```

```
length: 150
shape: (150, 5)
size: 750
min: 2.0
max: 4.4
mean: 3.0573333333333337
median: 3.0
50th percentile: 3.0
5th percentile: 2.3449999999999998
10th percentile: 2.5
95th percentile: 3.8
```

4. Use the `value_counts` function to show the number of items in each category, sorted from largest to smallest. You can also set the `ascending` argument to `True` to display the list from smallest to largest.

```
print(customerdf['industry'].value_counts())
print()
print(customerdf['industry'].value_counts(ascending=True))
```

```
academia      5
finance       2
retail        2
Name: industry, dtype: int64

retail        2
finance       2
academia      5
Name: industry, dtype: int64
```

Categorical variables

In statistics, a categorical variable may take on a limited number of possible values. Examples could include blood type, nation of origin, or ratings on a Likert scale.

Like numbers, the possible values may have an order, such as from `disagree` to `neutral` to `agree`. The values cannot, however, be used for numerical operations such as addition or division.

Categorical variables tell other Python libraries how to handle the data, so those libraries can default to suitable statistical methods or plot types.

The following example converts the `class` variable of the Iris dataset from `object` to `category`.

```
print(irisdf.dtypes)
print()
irisdf['class'] = irisdf['class'].astype('category')
print(irisdf.dtypes)
```

```
sepal_length    float64
sepal_width     float64
petal_length    float64
petal_width     float64
class           object
dtype: object

sepal_length    float64
sepal_width     float64
```

(continues on next page)

(continued from previous page)

```
petal_length    float64
petal_width     float64
class           category
dtype: object
```

Within Pandas, this creates an array of the possible values, where each value appears only once, and replaces the strings in the DataFrame with indexes into the array. In some cases, this saves significant memory.

A categorical variable may have a logical order different than the lexical order. For example, for ratings on a Likert scale, the *lexical* order could alphabetize the strings and produce agree, disagree, neither agree nor disagree, strongly agree, strongly disagree. The *logical* order could range from most negative to most positive as strongly disagree, disagree, neither agree nor disagree, agree, strongly agree.

Time series data visualization

The following code sample creates four series of random numbers over time, calculates the cumulative sums for each series over time, and plots them.

```
timedf = pd.DataFrame(np.random.randn(1000, 4), index=pd.date_range('1/1/2015',
→periods=1000), columns=list('ABCD'))
timedf = timedf.cumsum()
timedf.plot()
```




This example was adapted from <http://pandas.pydata.org/pandas-docs/stable/visualization.html>.

Histograms

This code sample plots a histogram of the sepal length values in the Iris data set:

```
plt.hist(irisdf['sepal_length'])
plt.show()
```



Bar charts

The following sample code produces a bar chart of the industries of customers in the customer data set.


```
industries = customerdf['industry'].value_counts()

fig, ax = plt.subplots()

ax.bar(np.arange(len(industries)), industries)

ax.set_xlabel('Industry')
ax.set_ylabel('Customers')
ax.set_title('Customer industries')
ax.set_xticks(np.arange(len(industries)))
ax.set_xticklabels(industries.index)

plt.show()
```




This example was adapted from https://matplotlib.org/gallery/statistics/barchart_demo.html.

Scatter plots

This code sample makes a scatter plot of the sepal lengths and widths in the Iris data set:

```
fig, ax = plt.subplots()
ax.scatter(irisdf['sepal_length'], irisdf['sepal_width'], color='green')
ax.set(
    xlabel="length",
    ylabel="width",
    title="Iris sepal sizes",
)
plt.show()
```



Sorting

To show the customer data set:

```
customerdf
```

row	customer_id	title	industry
0	1	data scientist	retail
1	2	data scientist	academia
2	3	compiler optimizer	academia
3	4	data scientist	finance
4	5	compiler optimizer	academia
5	6	data scientist	academia
6	7	compiler optimizer	academia
7	8	data scientist	retail
8	9	compiler optimizer	finance

To sort by industry and show the results:

```
customerdf.sort_values(by=['industry'])
```


row	customer_id	title	industry
1	2	data scientist	academia
2	3	compiler optimizer	academia
4	5	compiler optimizer	academia
5	6	data scientist	academia
6	7	compiler optimizer	academia
3	4	data scientist	finance
8	9	compiler optimizer	finance
0	1	data scientist	retail
7	8	data scientist	retail

To sort by industry and then title:

```
customerdf.sort_values(by=['industry', 'title'])
```

row	customer_id	title	industry
2	3	compiler optimizer	academia
4	5	compiler optimizer	academia
6	7	compiler optimizer	academia
1	2	data scientist	academia
5	6	data scientist	academia
8	9	compiler optimizer	finance
3	4	data scientist	finance
0	1	data scientist	retail
7	8	data scientist	retail

The `sort_values` function can also use the following arguments:

- `axis` to sort either rows or columns
- `ascending` to sort in either ascending or descending order
- `inplace` to perform the sorting operation in-place, without copying the data, which can save space
- `kind` to use the quicksort, merge sort, or heapsort algorithms
- `na_position` to sort not a number (NaN) entries at the end or beginning

Grouping

`customerdf.groupby('title')['customer_id'].count()` counts the items in each group, excluding missing values such as not-a-number values (NaN). Because there are no missing customer IDs, this is equivalent to `customerdf.groupby('title').size()`.

```
print(customerdf.groupby('title')['customer_id'].count())
print()
print(customerdf.groupby('title').size())
print()
print(customerdf.groupby(['title', 'industry']).size())
print()
print(customerdf.groupby(['industry', 'title']).size())
```

```

title
compiler optimizer      4
data scientist          5
Name: customer_id, dtype: int64

title
compiler optimizer      4
data scientist          5
dtype: int64

title      industry
compiler optimizer  academia    3
               finance    1
data scientist    academia    2
               finance    1
               retail    2
dtype: int64

industry  title
academia  compiler optimizer    3
          data scientist    2
finance   compiler optimizer    1
          data scientist    1
retail    data scientist    2
dtype: int64

```

By default `groupby` sorts the group keys. You can use the `sort=False` option to prevent this, which can make the grouping operation faster.

Binning

Binning or bucketing moves continuous data into discrete chunks, which can be used as ordinal categorical variables.

You can divide the range of the sepal length measurements into four equal bins:

```
pd.cut(irisdf['sepal_length'], 4).head()
```

```

0      (4.296, 5.2]
1      (4.296, 5.2]
2      (4.296, 5.2]
3      (4.296, 5.2]
4      (4.296, 5.2]
Name: sepal_length, dtype: category
Categories (4, interval[float64]): [(4.296, 5.2] < (5.2, 6.1] < (6.1, 7.0] < (7.0, 7.
↪9]]

```

Or make a custom bin array to divide the sepal length measurements into integer-sized bins from 4 through 8:

```
custom_bin_array = np.linspace(4, 8, 5)
custom_bin_array
```

```
array([4., 5., 6., 7., 8.])
```


Copy the Iris data set, and apply the binning to it:

```
iris2=irisdf.copy()
iris2['sepal_length'] = pd.cut(iris2['sepal_length'], custom_bin_array)
iris2['sepal_length'].head()
```

```
0      (5.0, 6.0]
1      (4.0, 5.0]
2      (4.0, 5.0]
3      (4.0, 5.0]
4      (4.0, 5.0]
Name: sepal_length, dtype: category
Categories (4, interval[float64]): [(4.0, 5.0] < (5.0, 6.0] < (6.0, 7.0] < (7.0, 8.0]]
```

Then plot the binned data:

```
plt.style.use('ggplot')
categories = iris2['sepal_length'].cat.categories
ind = np.array([x for x, _ in enumerate(categories)])
plt.bar(ind, iris2.groupby('sepal_length').size(), width=0.5, label='Sepal length')
plt.xticks(ind, categories)
plt.show()
```



This example was adapted from <http://benalexkeen.com/bucketing-continuous-variables-in-pandas/>.

3.5.3 Data preparation

Anaconda Enterprise supports data preparation using numeric libraries such as NumPy, SciPy, and Pandas.

These examples use this small data file `vendors.csv`:

```
Vendor Number, Vendor Name, Month, Day, Year, Active, Open Orders, 2015, 2016, Percent Growth
"104.0", ACME Inc, 2, 15, 2014, "Y", 200, "$45,000.00", $54000.00, 20.00%
205, Apogee LTD, 8, 12, 2015, "Y", 150, "$29,000.00", "$30,450.00", 5.00%
143, Zenith Co, 4, 5, 2014, "Y", 290, "$18,000.00", $23400.00, 30.00%
166, Hollerith Propulsion, 9, 25, 2015, "Y", 180, "$48,000.00", $48960.00, 2.00%
180, Airtex Industrial, 8, 2, 2014, "N", Closed, "$23,000.00", $17250.00, -25.00%
```

The columns are the vendor ID number, vendor name, month day and year of first purchase from the vendor, whether the account is currently active, the number of open orders, purchases in 2015 and 2016, and percent growth in orders from 2015 to 2016.

Converting data types

Computers handle many types of data, including integer numbers such as 365, floating point numbers such as 365.2425, strings such as “ACME Inc”, and more.

An operation such as division may work for integers and floating point numbers, but produce an error if used on strings.

Often data libraries such as pandas will automatically use the correct types, but they do provide ways to correct and change the types when needed. For example, you may wish to convert between an integer such as 25, the floating point number 25.0, and strings such as “25”, “25.0”, or “\$25.00”.

Pandas data types or `dtypes` correspond to similar Python types.

Strings are called `str` in Python and `object` in pandas.

Integers are called `int` in Python and `int64` in pandas, indicating that pandas stores integers as 64-bit numbers.

Floating point numbers are called `float` in Python and `float64` in pandas, also indicating that they are stored with 64 bits.

A boolean value, named for logician George Boole, can be either `True` or `False`. These are called `bool` in Python and `bool` in pandas.

Pandas includes some data types with no corresponding native Python type: `datetime64` for date and time values, `timedelta[ns]` for storing the difference between two times as a number of nanoseconds, and `category` where each item is one of a list of strings.

Here we import the vendor data file and show the `dtypes`:

```
import pandas as pd
import numpy as np
df = pd.read_csv('vendors.csv')
df.dtypes
```

```
Vendor Number    float64
Vendor Name      object
Month            int64
Day              int64
Year             int64
Active           object
Open Orders      object
2015             object
2016             object
Percent Growth   object
dtype: object
```

Try adding the 2015 and 2016 sales:

```
df['2015'] + df['2016']
```

```
0    $45,000.00$54000.00
1    $29,000.00$30,450.00
2    $18,000.00$23400.00
3    $48,000.00$48960.00
4    $23,000.00$17250.00
dtype: object
```

These columns were stored as the type “object”, and concatenated as strings, not added as numbers.

Examine more information about the `DataFrame`:

```
df.info()
```

```
<class 'pandas.core.frame.DataFrame'>
RangeIndex: 5 entries, 0 to 4
Data columns (total 10 columns):
Vendor Number      5 non-null float64
Vendor Name        5 non-null object
Month              5 non-null int64
Day                5 non-null int64
Year               5 non-null int64
Active             5 non-null object
Open Orders        5 non-null object
2015               5 non-null object
2016               5 non-null object
Percent Growth     5 non-null object
dtypes: float64(1), int64(3), object(6)
memory usage: 480.0+ bytes
```

Vendor Number is a float and not an int. 2015 and 2016 sales, percent growth, and open orders are stored as objects and not numbers. The month, day, and year values should be converted to `datetime64`, and the active column should be converted to a boolean.

The data can be converted with the `astype()` function, custom functions, or pandas functions such as `to_numeric()` or `to_datetime()`.

astype()

The `astype()` function can convert the Vendor Number column to `int`:

```
df['Vendor Number'].astype('int')
```

```
0    104
1    205
2    143
3    166
4    180
Name: Vendor Number, dtype: int64
```

`astype()` returns a copy, so an assignment statement will convert the original data. This can be checked by showing the dtypes.

```
df['Vendor Number'] = df['Vendor Number'].astype('int')
df.dtypes
```

```
Vendor Number      int64
Vendor Name        object
Month              int64
Day                int64
Year               int64
Active             object
Open Orders        object
2015               object
2016               object
Percent Growth     object
dtype: object
```

However, trying to convert the 2015 column to a `float` or the Open Orders column to an `int` returns an error.

```
df['2015'].astype('float')
```

```
ValueError: could not convert string to float: '$23,000.00'
```

```
df['Open Orders'].astype('int')
```

```
ValueError: invalid literal for int() with base 10: 'Closed'
```

Even worse, trying to convert the Active column to a `bool` completes with no errors, but converts both Y and N values to `True`.

```
df['Active'].astype('bool')
```

```
0    True
1    True
2    True
3    True
4    True
Name: Active, dtype: bool
```

`astype()` works if the data is clean and can be interpreted simply as a number, or if you want to convert a number to a string. Other conversions require custom functions or pandas functions such as `to_numeric()` or `to_datetime()`.

Custom conversion functions

This small custom function converts a currency string like the ones in the 2015 column to a `float` by first removing the comma (,) and dollar sign (\$) characters.

```
def currency_to_float(a):
    return float(a.replace(',', '').replace('$', ''))
```

Test the function on the 2015 column with the `apply()` function:

```
df['2015'].apply(currency_to_float)
```

```
0    45000.0
1    29000.0
2    18000.0
3    48000.0
4    23000.0
Name: 2015, dtype: float64
```

Convert the 2015 and 2016 columns and show the dtypes:

```
df['2015'] = df['2015'].apply(currency_to_float)
df['2016'] = df['2016'].apply(currency_to_float)
df.dtypes
```

```
Vendor Number    int64
Vendor Name      object
```

(continues on next page)

(continued from previous page)

```

Month          int64
Day            int64
Year           int64
Active         object
Open Orders    object
2015           float64
2016           float64
Percent Growth object
dtype: object

```

Convert the Percent Growth column:

```

def percent_to_float(a):
    return float(a.replace('%', '')) / 100
df['Percent Growth'].apply(percent_to_float)

```

```

0    0.20
1    0.05
2    0.30
3    0.02
4   -0.25
Name: Percent Growth, dtype: float64

```

```

df['Percent Growth'] = df['Percent Growth'].apply(percent_to_float)
df.dtypes

```

```

Vendor Number    int64
Vendor Name      object
Month            int64
Day              int64
Year             int64
Active           object
Open Orders      object
2015             float64
2016             float64
Percent Growth   float64
dtype: object

```

NumPy's `np.where()` function is a good way to convert the Active column to `bool`. This code converts “Y” values to True and all other values to False, then shows the dtypes:

```

np.where(df["Active"] == "Y", True, False)

```

```

array([ True,  True,  True,  True, False])

```

```

df["Active"] = np.where(df["Active"] == "Y", True, False)
df.dtypes

```

```

Vendor Number    int64
Vendor Name      object
Month            int64
Day              int64
Year             int64
Active           bool

```

(continues on next page)

(continued from previous page)

```
Open Orders      object
2015             float64
2016             float64
Percent Growth   float64
dtype: object
```

Pandas helper functions

The Open Orders column has several integers, but one string. Using `astype()` on this column would produce an error, but the `pd.to_numeric()` function built in to pandas will convert the numeric values to numbers and any other values to the “not a number” or “NaN” value built in to the floating point number standard:

```
pd.to_numeric(df['Open Orders'], errors='coerce')
```

```
0    200.0
1    150.0
2    290.0
3    180.0
4      NaN
Name: Open Orders, dtype: float64
```

In this case, a non-numeric value in this field indicates that there are zero open orders, so we can convert NaN values to zero with the function `fillna()`:

```
pd.to_numeric(df['Open Orders'], errors='coerce').fillna(0)
```

```
0    200.0
1    150.0
2    290.0
3    180.0
4      0.0
Name: Open Orders, dtype: float64
```

Similarly, the `pd.to_datetime()` function built in to pandas can convert the Month Day and Year columns to `datetime64[ns]`:

```
pd.to_datetime(df[['Month', 'Day', 'Year']])
```

```
0    2014-02-15
1    2015-08-12
2    2014-04-05
3    2015-09-25
4    2014-08-02
dtype: datetime64[ns]
```

Use these functions to change the DataFrame, then show the dtypes:

```
df['Open Orders'] = pd.to_numeric(df['Open Orders'], errors='coerce').fillna(0)
df['First Purchase Date'] = pd.to_datetime(df[['Month', 'Day', 'Year']])
df.dtypes
```

```
Vendor Number      int64
Vendor Name        object
```

(continues on next page)

(continued from previous page)

```

Month                int64
Day                  int64
Year                 int64
Active               bool
Open Orders          float64
2015                  float64
2016                  float64
Percent Growth       float64
First Purchase Date  datetime64[ns]
dtype: object

```

Converting data as it is read

You can apply `dtype` and `converters` in the `pd.read_csv()` function. Defining `dtype` is like performing `astype()` on the data.

A `dtype` or a `converter` can only be applied once to a specified column. If you try to apply both to the same column, the `dtype` is skipped.

After converting as much of the data as possible in `pd.read_csv()`, use code similar to the previous examples to convert the rest.

```

df2 = pd.read_csv('vendors.csv',
                  dtype={'Vendor Number': 'int'},
                  converters={'2015': currency_to_float,
                              '2016': currency_to_float,
                              'Percent Growth': percent_to_float})
df2["Active"] = np.where(df2["Active"] == "Y", True, False)
df2['Open Orders'] = pd.to_numeric(df2['Open Orders'], errors='coerce').fillna(0)
df2['First Purchase Date'] = pd.to_datetime(df2[['Month', 'Day', 'Year']])
df2

```

	Vendor Number		Vendor Name	Month	Day	Year	Active	Open Orders	
↪2015	2016	Percent Growth	First Purchase Date						
0	104		ACME Inc	2	15	2014	True	200.0	45000.
↪0	54000.0	0.20				2014-02-15			
1	205		Apogee LTD	8	12	2015	True	150.0	29000.
↪0	30450.0	0.05				2015-08-12			
2	143		Zenith Co	4	5	2014	True	290.0	18000.
↪0	23400.0	0.30				2014-04-05			
3	166		Hollerith Propulsion	9	25	2015	True	180.0	48000.
↪0	48960.0	0.02				2015-09-25			
4	180		Airtek Industrial	8	2	2014	False	0.0	23000.
↪0	17250.0	-0.25				2014-08-02			

```
df2.dtypes
```

```

Vendor Number      int64
Vendor Name         object
Month               int64
Day                 int64
Year                int64
Active              bool
Open Orders         float64

```

(continues on next page)

(continued from previous page)

```

2015                                float64
2016                                float64
Percent Growth                      float64
First Purchase Date    datetime64[ns]
dtype: object

```

We thank http://pbpython.com/pandas_dtypes.html for providing data preparation examples that inspired these examples.

Merging and joining data sets

You can use pandas to merge DataFrames:

```

left = pd.DataFrame({'key': ['K0', 'K1', 'K2', 'K3'],
                     'A': ['A0', 'A1', 'A2', 'A3'],
                     'B': ['B0', 'B1', 'B2', 'B3']})
right = pd.DataFrame({'key': ['K0', 'K1', 'K2', 'K3'],
                     'C': ['C0', 'C1', 'C2', 'C3'],
                     'D': ['D0', 'D1', 'D2', 'D3']})
pd.merge(left, right, on='key')

```

	key	A	B	C	D
0	K0	A0	B0	C0	D0
1	K1	A1	B1	C1	D1
2	K2	A2	B2	C2	D2
3	K3	A3	B3	C3	D3

The available merge methods are `left` to use keys from the left frame only, `right` to use keys from the right frame only, `outer` to use the union of keys from both frames, and the default `inner` to use the intersection of keys from both frames.

This merge using the default inner join omits key combinations found in only one of the source DataFrames:

```

left = pd.DataFrame({'key1': ['K0', 'K0', 'K1', 'K2'],
                     'key2': ['K0', 'K1', 'K0', 'K1'],
                     'A': ['A0', 'A1', 'A2', 'A3'],
                     'B': ['B0', 'B1', 'B2', 'B3']})
right = pd.DataFrame({'key1': ['K0', 'K1', 'K1', 'K2'],
                     'key2': ['K0', 'K0', 'K0', 'K0'],
                     'C': ['C0', 'C1', 'C2', 'C3'],
                     'D': ['D0', 'D1', 'D2', 'D3']})
pd.merge(left, right, on=['key1', 'key2'])

```

	key1	key2	A	B	C	D
0	K0	K0	A0	B0	C0	D0
1	K1	K0	A2	B2	C1	D1
2	K1	K0	A2	B2	C2	D2

This example omits the rows with `key1` and `key2` set to `K0`, `K1`, `K2`, `K1`, or `K2`, `K0`.

Joins also copy information when necessary. The left DataFrame had one row with the keys set to `K1`, `K0` and the right DataFrame had two. The output DataFrame has two, with the information from the left DataFrame copied into both rows.

The next example shows the results of a left, right, and outer merge on the same inputs. Empty cells are filled in with NaN values.

```
pd.merge(left, right, how='left', on=['key1', 'key2'])
```

	key1	key2	A	B	C	D
0	K0	K0	A0	B0	C0	D0
1	K0	K1	A1	B1	NaN	NaN
2	K1	K0	A2	B2	C1	D1
3	K1	K0	A2	B2	C2	D2
4	K2	K1	A3	B3	NaN	NaN

```
pd.merge(left, right, how='right', on=['key1', 'key2'])
```

	key1	key2	A	B	C	D
0	K0	K0	A0	B0	C0	D0
1	K1	K0	A2	B2	C1	D1
2	K1	K0	A2	B2	C2	D2
3	K2	K0	NaN	NaN	C3	D3

```
pd.merge(left, right, how='outer', on=['key1', 'key2'])
```

	key1	key2	A	B	C	D
0	K0	K0	A0	B0	C0	D0
1	K0	K1	A1	B1	NaN	NaN
2	K1	K0	A2	B2	C1	D1
3	K1	K0	A2	B2	C2	D2
4	K2	K1	A3	B3	NaN	NaN
5	K2	K0	NaN	NaN	C3	D3

If a key combination appears more than once in both tables, the output will contain the Cartesian product of the associated data.

In this small example a key that appears twice in the left frame and three times in the right frame produces six rows in the output frame.

```
left = pd.DataFrame({'A': [1,2], 'B': [2, 2]})
right = pd.DataFrame({'A': [4,5,6], 'B': [2,2,2]})
pd.merge(left, right, on='B', how='outer')
```

	A_x	B	A_y
0	1	2	4
1	1	2	5
2	1	2	6
3	2	2	4
4	2	2	5
5	2	2	6

To prevent very large outputs and memory overflow, manage duplicate values in keys before joining large DataFrames.

While merging uses one or more columns as keys, joining uses the indexes, also known as row labels.

Join can also perform left, right, inner, and outer merges, and defaults to left.

```
left = pd.DataFrame({'A': ['A0', 'A1', 'A2'],
                     'B': ['B0', 'B1', 'B2']},
                    index=['K0', 'K1', 'K2'])
right = pd.DataFrame({'C': ['C0', 'C2', 'C3'],
                     'D': ['D0', 'D2', 'D3']},
```

(continues on next page)

(continued from previous page)

```

                                index=['K0', 'K2', 'K3'])
left.join(right)

```

	A	B	C	D
K0	A0	B0	C0	D0
K1	A1	B1	NaN	NaN
K2	A2	B2	C2	D2

```
left.join(right, how='outer')
```

	A	B	C	D
K0	A0	B0	C0	D0
K1	A1	B1	NaN	NaN
K2	A2	B2	C2	D2
K3	NaN	NaN	C3	D3

```
left.join(right, how='inner')
```

	A	B	C	D
K0	A0	B0	C0	D0
K2	A2	B2	C2	D2

This is equivalent to using merge with arguments instructing it to use the indexes:

```
pd.merge(left, right, left_index=True, right_index=True, how='inner')
```

	A	B	C	D
K0	A0	B0	C0	D0
K2	A2	B2	C2	D2

You can join a frame indexed by a join key to a frame where the key is a column:

```

left = pd.DataFrame({'A': ['A0', 'A1', 'A2', 'A3'],
                     'B': ['B0', 'B1', 'B2', 'B3'],
                     'key': ['K0', 'K1', 'K0', 'K1']})
right = pd.DataFrame({'C': ['C0', 'C1'],
                     'D': ['D0', 'D1']},
                     index=['K0', 'K1'])
left.join(right, on='key')

```

	A	B	key	C	D
0	A0	B0	K0	C0	D0
1	A1	B1	K1	C1	D1
2	A2	B2	K0	C0	D0
3	A3	B3	K1	C1	D1

You can join on multiple keys if the passed DataFrame has a MultiIndex:

```

left = pd.DataFrame({'A': ['A0', 'A1', 'A2', 'A3'],
                     'B': ['B0', 'B1', 'B2', 'B3'],
                     'key1': ['K0', 'K0', 'K1', 'K2'],
                     'key2': ['K0', 'K1', 'K0', 'K1']})
index = pd.MultiIndex.from_tuples([('K0', 'K0'), ('K1', 'K0'),
                                   ('K2', 'K0'), ('K2', 'K1')])

```

(continues on next page)

(continued from previous page)

```
right = pd.DataFrame({'C': ['C0', 'C1', 'C2', 'C3'],
                      'D': ['D0', 'D1', 'D2', 'D3']},
                      index=index)
right
```

```
      C  D
K0 K0  C0  D0
K1 K0  C1  D1
K2 K0  C2  D2
    K1  C3  D3
```

```
left.join(right, on=['key1', 'key2'])
```

```
   A  B key1 key2  C  D
0  A0 B0   K0  K0  C0 D0
1  A1 B1   K0  K1  NaN NaN
2  A2 B2   K1  K0  C1 D1
3  A3 B3   K2  K1  C3 D3
```

Note that this defaulted to a left join, but other types are also available:

```
left.join(right, on=['key1', 'key2'], how='inner')
```

```
   A  B key1 key2  C  D
0  A0 B0   K0  K0  C0 D0
2  A2 B2   K1  K0  C1 D1
3  A3 B3   K2  K1  C3 D3
```

For more information, including examples of using merge to join a single index to a multi-index or to join two multi-indexes, see the [pandas documentation on merging](#).

When column names in the input frames overlap, pandas appends suffixes to disambiguate them. These default to `_x` and `_y` but you can customize them:

```
left = pd.DataFrame({'k': ['K0', 'K1', 'K2'], 'v': [1, 2, 3]})
right = pd.DataFrame({'k': ['K0', 'K0', 'K3'], 'v': [4, 5, 6]})
pd.merge(left, right, on='k')
```

```
   k  v_x  v_y
0  K0    1    4
1  K0    1    5
```

```
pd.merge(left, right, on='k', suffixes=['_l', '_r'])
```

```
   k  v_l  v_r
0  K0    1    4
1  K0    1    5
```

Join has similar arguments `lsuffix` and `rsuffix`.

```
left = left.set_index('k')
right = right.set_index('k')
left.join(right, lsuffix='_l', rsuffix='_r')
```

```
      v_l  v_r
k
K0      1  4.0
K0      1  5.0
K1      2  NaN
K2      3  NaN
```

You can join a list or tuple of DataFrames on their indexes:

```
right2 = pd.DataFrame({'v': [7, 8, 9]}, index=['K1', 'K1', 'K2'])
left.join([right, right2])
```

```
      v_x  v_y  v
K0      1  4.0 NaN
K0      1  5.0 NaN
K1      2  NaN  7.0
K1      2  NaN  8.0
K2      3  NaN  9.0
```

If you have two frames with similar indices and want to fill in missing values in the left frame with values from the right frame, use the `combine_first()` method:

```
df1 = pd.DataFrame([[np.nan, 3., 5.],
                    [-4.6, np.nan, np.nan],
                    [np.nan, 7., np.nan]])
df2 = pd.DataFrame([[ -42.6, np.nan, -8.2],
                    [-5., 1.6, 4]],
                    index=[1, 2])
df1.combine_first(df2)
```

```
      0      1      2
0  NaN  3.0  5.0
1 -4.6  NaN -8.2
2 -5.0  7.0  4.0
```

The method `update()` overwrites values in a frame with values from another frame:

```
df1.update(df2)
df1
```

```
      0      1      2
0  NaN  3.0  5.0
1 -42.6  NaN -8.2
2 -5.0  1.6  4.0
```

The [pandas documentation on merging](#) has more information, including examples of combining time series and other ordered data, with options to fill and interpolate missing data.

We thank the pandas documentation for many of these examples.

Filtering data

This example uses a vendors DataFrame similar to the one we used above:

```
import pandas as pd
import numpy as np
df = pd.DataFrame({'VendorNumber': [104, 205, 143, 166, 180],
                   'VendorName': ['ACME Inc', 'Apogee LTD', 'Zenith Co', 'Hollerith_
↳Propulsion', 'Airtek Industrial'],
                   'Active': [True, True, True, True, False],
                   'OpenOrders': [200, 150, 290, 180, 0],
                   'Purchases2015': [45000.0, 29000.0, 18000.0, 48000.0, 23000.0],
                   'Purchases2016': [54000.0, 30450.0, 23400.0, 48960.0, 17250.0],
                   'PercentGrowth': [0.20, 0.05, 0.30, 0.02, -0.25],
                   'FirstPurchaseDate': ['2014-02-15', '2015-08-12', '2014-04-05', '2015-
↳09-25', '2014-08-02']})
df['FirstPurchaseDate'] = df['FirstPurchaseDate'].astype('datetime64[ns]')
df
```

	VendorNumber		VendorName	Active	OpenOrders	Purchases2015	↳
	↳Purchases2016	PercentGrowth	FirstPurchaseDate				
0	104		ACME Inc	True	200	45000.0	54000.
↳0		0.20	2014-02-15				
1	205		Apogee LTD	True	150	29000.0	30450.
↳0		0.05	2015-08-12				
2	143		Zenith Co	True	290	18000.0	23400.
↳0		0.30	2014-04-05				
3	166	Hollerith	Propulsion	True	180	48000.0	48960.
↳0		0.02	2015-09-25				
4	180	Airtek	Industrial	False	0	23000.0	17250.
↳0		-0.25	2014-08-02				

To filter only certain rows from a DataFrame, call the `query` method with a boolean expression based on the column names.

```
df.query('OpenOrders>160')
```

	VendorNumber		VendorName	Active	OpenOrders	Purchases2015	↳
	↳Purchases2016	PercentGrowth	FirstPurchaseDate				
0	104		ACME Inc	True	200	45000.0	54000.
↳0		0.20	2014-02-15				
2	143		Zenith Co	True	290	18000.0	23400.
↳0		0.30	2014-04-05				
3	166	Hollerith	Propulsion	True	180	48000.0	48960.
↳0		0.02	2015-09-25				

Filtering can be done with indices instead of queries:

```
df[(df.OpenOrders < 190) & (df.Active == True)]
```

	VendorNumber		VendorName	Active	OpenOrders	Purchases2015	↳
	↳Purchases2016	PercentGrowth	FirstPurchaseDate				
1	205		Apogee LTD	True	150	29000.0	30450.
↳0		0.05	2015-08-12				
3	166	Hollerith	Propulsion	True	180	48000.0	48960.
↳0		0.02	2015-09-25				

3.5.4 Using statistics

Anaconda Enterprise supports statistical work using the R language and Python libraries such as NumPy, SciPy, Pandas, Statsmodels, and scikit-learn.

The following Jupyter notebook Python examples show how to use these libraries to calculate correlations, distributions, regressions, and principal component analysis.

These examples also include plots produced with the libraries seaborn and Matplotlib.

We thank these sites, from whom we have adapted some code:

- <https://stackoverflow.com/questions/25571882/pandas-columns-correlation-with-statistical-significance/49040342>
- <https://joomik.github.io/Housing/>

Start by importing necessary libraries and functions, including Pandas, SciPy, scikit-learn, Statsmodels, seaborn, and Matplotlib.

This code imports `load_boston` to provide the Boston housing dataset from the datasets included with scikit-learn.

```
import pandas as pd
import seaborn as sns
from scipy.stats import pearsonr
from sklearn.datasets import load_boston
from sklearn.linear_model import LinearRegression
from sklearn.metrics import mean_squared_error
from sklearn.model_selection import train_test_split
from sklearn.preprocessing import StandardScaler
from sklearn.decomposition import PCA
import matplotlib.pyplot as plt
from mpl_toolkits.mplot3d import Axes3D
import statsmodels.formula.api as sm

%matplotlib inline
```

Load the Boston housing data into a Pandas DataFrame:

```
#Load dataset and convert it to a Pandas dataframe
boston = load_boston()
df = pd.DataFrame(boston.data, columns=boston.feature_names)
df['target'] = boston.target
```

In the Boston housing dataset, the target variable is MEDV, the median home value.

Print the dataset description:

```
#Description of the dataset
print(boston.DESCR)
```

```
Boston House Prices dataset
=====

Notes
-----
Data Set Characteristics:

:Number of Instances: 506
```

(continues on next page)

(continued from previous page)

```
:Number of Attributes: 13 numeric/categorical predictive

:Median Value (attribute 14) is usually the target

:Attribute Information (in order):
- CRIM      per capita crime rate by town
- ZN        proportion of residential land zoned for lots over 25,000 sq.ft.
- INDUS     proportion of non-retail business acres per town
- CHAS      Charles River dummy variable (= 1 if tract bounds river; 0 otherwise)
- NOX       nitric oxides concentration (parts per 10 million)
- RM        average number of rooms per dwelling
- AGE       proportion of owner-occupied units built prior to 1940
- DIS       weighted distances to five Boston employment centres
- RAD       index of accessibility to radial highways
- TAX       full-value property-tax rate per $10,000
- PTRATIO   pupil-teacher ratio by town
- B         1000(Bk - 0.63)^2 where Bk is the proportion of blacks by town
- LSTAT     % lower status of the population
- MEDV      Median value of owner-occupied homes in $1000's
```

```
:Missing Attribute Values: None
```

```
:Creator: Harrison, D. and Rubinfeld, D.L.
```

```
This is a copy of UCI ML housing dataset.
http://archive.ics.uci.edu/ml/datasets/Housing
```

```
This dataset was taken from the StatLib library which is maintained at Carnegie_
↳ Mellon University.
```

```
The Boston house-price data of Harrison, D. and Rubinfeld, D.L. 'Hedonic
prices and the demand for clean air', J. Environ. Economics & Management,
vol.5, 81-102, 1978.  Used in Belsley, Kuh & Welsch, 'Regression diagnostics
...', Wiley, 1980.  N.B. Various transformations are used in the table on
pages 244-261 of the latter.
```

```
The Boston house-price data has been used in many machine learning papers that_
↳ address regression
problems.
```

```
**References**
```

```
- Belsley, Kuh & Welsch, 'Regression diagnostics: Identifying Influential Data and_
↳ Sources of Collinearity', Wiley, 1980. 244-261.
- Quinlan, R. (1993). Combining Instance-Based and Model-Based Learning. In_
↳ Proceedings on the Tenth International Conference of Machine Learning, 236-243,_
↳ University of Massachusetts, Amherst. Morgan Kaufmann.
- many more! (see http://archive.ics.uci.edu/ml/datasets/Housing)
```

Show the first five records of the dataset:

```
#Check the first five records
df.head()
```

```
row CRIM      ZN      INDUS CHAS NOX      RM      AGE      DIS      RAD TAX      PTRATIO B      LSTAT_
↳ target
```

(continues on next page)

(continued from previous page)

```

=====
↪=====
0  0.00632 18.0 2.31  0.0  0.538 6.575 65.2 4.0900 1.0 296.0 15.3  396.90 4.98 24.
↪0
1  0.02731 0.0  7.07  0.0  0.469 6.421 78.9 4.9671 2.0 242.0 17.8  396.90 9.14 21.
↪6
2  0.02729 0.0  7.07  0.0  0.469 7.185 61.1 4.9671 2.0 242.0 17.8  392.83 4.03 34.
↪7
3  0.03237 0.0  2.18  0.0  0.458 6.998 45.8 6.0622 3.0 222.0 18.7  394.63 2.94 33.
↪4
4  0.06905 0.0  2.18  0.0  0.458 7.147 54.2 6.0622 3.0 222.0 18.7  396.90 5.33 36.
↪2

```

Show summary statistics for each variable: count, mean, standard deviation, minimum, 25th 50th and 75th percentiles, and maximum.

```

#Descriptions of each variable
df.describe()

```

```

stat  CRIM      ZN      INDUS      CHAS      NOX      RM      AGE
↪DIS      RAD      TAX      PTRATIO      B      LSTAT      target
=====
↪=====
count 506.000000 506.000000 506.000000 506.000000 506.000000 506.000000 506.000000
↪506.000000 506.000000 506.000000 506.000000 506.000000 506.000000 506.000000
mean  3.593761  11.363636  11.136779  0.069170  0.554695  6.284634  68.574901  3.
↪795043  9.549407  408.237154 18.455534  356.674032 12.653063  22.532806
std   8.596783  23.322453  6.860353  0.253994  0.115878  0.702617  28.148861  2.
↪105710  8.707259  168.537116 2.164946  91.294864  7.141062  9.197104
min   0.006320  0.000000  0.460000  0.000000  0.385000  3.561000  2.900000  1.
↪129600  1.000000  187.000000 12.600000  0.320000  1.730000  5.000000
25%   0.082045  0.000000  5.190000  0.000000  0.449000  5.885500  45.025000  2.
↪100175  4.000000  279.000000 17.400000  375.377500 6.950000  17.025000
50%   0.256510  0.000000  9.690000  0.000000  0.538000  6.208500  77.500000  3.
↪207450  5.000000  330.000000 19.050000  391.440000 11.360000  21.200000
75%   3.647423  12.500000  18.100000  0.000000  0.624000  6.623500  94.075000  5.
↪188425  24.000000  666.000000 20.200000  396.225000 16.955000  25.000000
max   88.976200 100.000000 27.740000  1.000000  0.871000  8.780000  100.000000 12.
↪126500  24.000000  711.000000 22.000000  396.900000 37.970000  50.000000

```

Correlation matrix

The correlation matrix lists the correlation of each variable with each other variable.

Positive correlations mean one variable tends to be high when the other is high, and negative correlations mean one variable tends to be high when the other is low.

Correlations close to zero are weak and cause a variable to have less influence in the model, and correlations close to one or negative one are strong and cause a variable to have more influence in the model.

```

#Here shows the basic correlation matrix
corr = df.corr()
corr

```

variable	CRIM	ZN	INDUS	CHAS	NOX	RM	AGE	DIS
→ RAD	TAX		PTRATIO	B	LSTAT	target		
CRIM	1.000000	-0.199458	0.404471	-0.055295	0.417521	-0.219940	0.350784	-0.
→377904	0.622029	0.579564	0.288250	-0.377365	0.452220	-0.385832		
ZN	-0.199458	1.000000	-0.533828	-0.042697	-0.516604	0.311991	-0.569537	0.
→664408	-0.311948	-0.314563	-0.391679	0.175520	-0.412995	0.360445		
INDUS	0.404471	-0.533828	1.000000	0.062938	0.763651	-0.391676	0.644779	-0.
→708027	0.595129	0.720760	0.383248	-0.356977	0.603800	-0.483725		
CHAS	-0.055295	-0.042697	0.062938	1.000000	0.091203	0.091251	0.086518	-0.
→099176	-0.007368	-0.035587	-0.121515	0.048788	-0.053929	0.175260		
NOX	0.417521	-0.516604	0.763651	0.091203	1.000000	-0.302188	0.731470	-0.
→769230	0.611441	0.668023	0.188933	-0.380051	0.590879	-0.427321		
RM	-0.219940	0.311991	-0.391676	0.091251	-0.302188	1.000000	-0.240265	0.
→205246	-0.209847	-0.292048	-0.355501	0.128069	-0.613808	0.695360		
AGE	0.350784	-0.569537	0.644779	0.086518	0.731470	-0.240265	1.000000	-0.
→747881	0.456022	0.506456	0.261515	-0.273534	0.602339	-0.376955		
DIS	-0.377904	0.664408	-0.708027	-0.099176	-0.769230	0.205246	-0.747881	1.
→000000	-0.494588	-0.534432	-0.232471	0.291512	-0.496996	0.249929		
RAD	0.622029	-0.311948	0.595129	-0.007368	0.611441	-0.209847	0.456022	-0.
→494588	1.000000	0.910228	0.464741	-0.444413	0.488676	-0.381626		
TAX	0.579564	-0.314563	0.720760	-0.035587	0.668023	-0.292048	0.506456	-0.
→534432	0.910228	1.000000	0.460853	-0.441808	0.543993	-0.468536		
PTRATIO	0.288250	-0.391679	0.383248	-0.121515	0.188933	-0.355501	0.261515	-0.
→232471	0.464741	0.460853	1.000000	-0.177383	0.374044	-0.507787		
B	-0.377365	0.175520	-0.356977	0.048788	-0.380051	0.128069	-0.273534	0.
→291512	-0.444413	-0.441808	-0.177383	1.000000	-0.366087	0.333461		
LSTAT	0.452220	-0.412995	0.603800	-0.053929	0.590879	-0.613808	0.602339	-0.
→496996	0.488676	0.543993	0.374044	-0.366087	1.000000	-0.737663		
target	-0.385832	0.360445	-0.483725	0.175260	-0.427321	0.695360	-0.376955	0.
→249929	-0.381626	-0.468536	-0.507787	0.333461	-0.737663	1.000000		

Format with asterisks

Format the correlation matrix by rounding the numbers to two decimal places and adding asterisks to denote statistical significance:

```
def calculate_pvalues(df):
    df = df.select_dtypes(include=['number'])
    pairs = pd.MultiIndex.from_product([df.columns, df.columns])
    pvalues = [pearsonr(df[a], df[b])[1] for a, b in pairs]
    pvalues = pd.Series(pvalues, index=pairs).unstack().round(4)
    return pvalues

# code adapted from https://stackoverflow.com/questions/25571882/pandas-columns-
# correlation-with-statistical-significance/49040342
def correlation_matrix(df, columns):
    rho = df[columns].corr()
    pval = calculate_pvalues(df[columns])
    # create three masks
    r0 = rho.applymap(lambda x: '{:.2f}'.format(x))
    r1 = rho.applymap(lambda x: '{:.2f}*'.format(x))
    r2 = rho.applymap(lambda x: '{:.2f}**'.format(x))
    r3 = rho.applymap(lambda x: '{:.2f}***'.format(x))
```

(continues on next page)

(continued from previous page)

```

# apply marks
rho = rho.mask(pval>0.01,r0)
rho = rho.mask(pval<=0.1,r1)
rho = rho.mask(pval<=0.05,r2)
rho = rho.mask(pval<=0.01,r3)
return rho

columns = df.columns
correlation_matrix(df,columns)

```

variable	CRIM	ZN	INDUS	CHAS	NOX	RM	AGE	DIS	RAD
TAX	PTRATIO	B	LSTAT	target					
CRIM	1.00***	-0.20***	0.40***	-0.06	0.42***	-0.22***	0.35***	-0.38***	0.
62***	0.58***	0.29***	-0.38***	0.45***	-0.39***				
ZN	-0.20***	1.00***	-0.53***	-0.04	-0.52***	0.31***	-0.57***	0.66***	-0.
31***	-0.31***	-0.39***	0.18***	-0.41***	0.36***				
INDUS	0.40***	-0.53***	1.00***	0.06	0.76***	-0.39***	0.64***	-0.71***	0.
60***	0.72***	0.38***	-0.36***	0.60***	-0.48***				
CHAS	-0.06	-0.04	0.06	1.00***	0.09**	0.09**	0.09*	-0.10**	-0.
01	-0.04	-0.12***	0.05	-0.05	0.18***				
NOX	0.42***	-0.52***	0.76***	0.09**	1.00***	-0.30***	0.73***	-0.77***	0.
61***	0.67***	0.19***	-0.38***	0.59***	-0.43***				
RM	-0.22***	0.31***	-0.39***	0.09**	-0.30***	1.00***	-0.24***	0.21***	-0.
21***	-0.29***	-0.36***	0.13***	-0.61***	0.70***				
AGE	0.35***	-0.57***	0.64***	0.09*	0.73***	-0.24***	1.00***	-0.75***	0.
46***	0.51***	0.26***	-0.27***	0.60***	-0.38***				
DIS	-0.38***	0.66***	-0.71***	-0.10**	-0.77***	0.21***	-0.75***	1.00***	-0.
49***	-0.53***	-0.23***	0.29***	-0.50***	0.25***				
RAD	0.62***	-0.31***	0.60***	-0.01	0.61***	-0.21***	0.46***	-0.49***	1.
00***	0.91***	0.46***	-0.44***	0.49***	-0.38***				
TAX	0.58***	-0.31***	0.72***	-0.04	0.67***	-0.29***	0.51***	-0.53***	0.
91***	1.00***	0.46***	-0.44***	0.54***	-0.47***				
PTRATIO	0.29***	-0.39***	0.38***	-0.12***	0.19***	-0.36***	0.26***	-0.23***	0.
46***	0.46***	1.00***	-0.18***	0.37***	-0.51***				
B	-0.38***	0.18***	-0.36***	0.05	-0.38***	0.13***	-0.27***	0.29***	-0.
44***	-0.44***	-0.18***	1.00***	-0.37***	0.33***				
LSTAT	0.45***	-0.41***	0.60***	-0.05	0.59***	-0.61***	0.60***	-0.50***	0.
49***	0.54***	0.37***	-0.37***	1.00***	-0.74***				
target	-0.39***	0.36***	-0.48***	0.18***	-0.43***	0.70***	-0.38***	0.25***	-0.
38***	-0.47***	-0.51***	0.33***	-0.74***	1.00***				


Heatmap

Heatmap of the correlation matrix:

```

sns.heatmap(corr,
             xticklabels=corr.columns,
             yticklabels=corr.columns)

```



Pairwise distributions with seaborn

```
sns.pairplot(df[['RM', 'AGE', 'TAX', 'target']])
```

Target variable distribution

Histogram showing the distribution of the target variable. In this dataset this is “Median value of owner-occupied homes in \$1000’s”, abbreviated MEDV.

```
plt.hist(df['target'])
plt.show()
```

Simple linear regression

The variable MEDV is the target that the model predicts. All other variables are used as predictors, also called features. The target variable is continuous, so use a linear regression instead of a logistic regression.



```
# Define features as X, target as y.
X = df.drop('target', axis='columns')
y = df['target']
```

Split the dataset into a training set and a test set:

```
# Splitting the dataset into training set and test set
X_train, X_test, y_train, y_test = train_test_split(X, y, test_size = 0.25, random_
→ state = 0)
```

A linear regression consists of a coefficient for each feature and one intercept.

To make a prediction, each feature is multiplied by its coefficient. The intercept and all of these products are added together. This sum is the predicted value of the target variable.



The residual sum of squares (RSS) is calculated to measure the difference between the prediction and the actual value of the target variable.

The function `fit` calculates the coefficients and intercept that minimize the RSS when the regression is used on each record in the training set.

```
# Fitting Simple Linear Regression to the Training set
from sklearn.linear_model import LinearRegression
regressor = LinearRegression()
regressor.fit(X_train, y_train)

# The intercept
print('Intercept: \n', regressor.intercept_)

# The coefficients
print('Coefficients: \n', pd.Series(regressor.coef_, index=X.columns, name=
→ 'coefficients'))
```


```
Intercept:
    36.98045533762056
Coefficients:
    CRIM      -0.116870
    ZN         0.043994
    INDUS     -0.005348
    CHAS       2.394554
    NOX      -15.629837
    RM         3.761455
    AGE       -0.006950
    DIS       -1.435205
    RAD        0.239756
    TAX       -0.011294
    PTRATIO   -0.986626
    B          0.008557
    LSTAT     -0.500029
Name: coefficients, dtype: float64
```

Now check the accuracy when this linear regression is used on new data that it was not trained on. That new data is the test set.

```
# Predicting the Test set results
y_pred = regressor.predict(X_test)

# Visualising the Test set results
# code adapted from https://joomik.github.io/Housing/
fig, ax = plt.subplots()
ax.scatter(y_test, y_pred, color='green')
ax.set(
    xlabel="Prices: $Y_i$",
    ylabel="Predicted prices: $\hat{Y}_i$",
    title="Prices vs Predicted prices: $Y_i$ vs $\hat{Y}_i$",
)
plt.show()
```

This scatter plot shows that the regression is a good predictor of the data in the test set.



The mean squared error quantifies this performance:

```
# The mean squared error as a way to measure model performance.
print("Mean squared error: %.2f" % mean_squared_error(y_test, y_pred))
```

```
Mean squared error: 29.79
```

Ordinary least squares (OLS) regression with Statsmodels

```
model = sm.ols('target ~ AGE + B + CHAS + CRIM + DIS + INDUS + LSTAT + NOX + PTRATIO_
↪+ RAD + RM + TAX + ZN', df)
result = model.fit()
result.summary()
```

OLS Regression Results

```
=====
Dep. Variable:          target    R-squared:                0.741
Model:                  OLS      Adj. R-squared:           0.734
Method:                 Least Squares    F-statistic:           108.1
Date:                   Thu, 23 Aug 2018    Prob (F-statistic):     6.95e-135
Time:                   07:29:16    Log-Likelihood:        -1498.8
No. Observations:       506    AIC:                   3026.
Df Residuals:           492    BIC:                   3085.
Df Model:                13
Covariance Type:        nonrobust
=====
```

	coef	std err	t	P> t	[0.025	0.975]
Intercept	36.4911	5.104	7.149	0.000	26.462	46.520
AGE	0.0008	0.013	0.057	0.955	-0.025	0.027
B	0.0094	0.003	3.500	0.001	0.004	0.015
CHAS	2.6886	0.862	3.120	0.002	0.996	4.381
CRIM	-0.1072	0.033	-3.276	0.001	-0.171	-0.043
DIS	-1.4758	0.199	-7.398	0.000	-1.868	-1.084
INDUS	0.0209	0.061	0.339	0.735	-0.100	0.142
LSTAT	-0.5255	0.051	-10.366	0.000	-0.625	-0.426
NOX	-17.7958	3.821	-4.658	0.000	-25.302	-10.289
PTRATIO	-0.9535	0.131	-7.287	0.000	-1.211	-0.696
RAD	0.3057	0.066	4.608	0.000	0.175	0.436
RM	3.8048	0.418	9.102	0.000	2.983	4.626
TAX	-0.0123	0.004	-3.278	0.001	-0.020	-0.005

(continues on next page)

(continued from previous page)

```

ZN          0.0464      0.014      3.380      0.001      0.019      0.073
=====
Omnibus:                178.029    Durbin-Watson:                1.078
Prob(Omnibus) :          0.000    Jarque-Bera (JB) :          782.015
Skew:                  1.521    Prob(JB) :                1.54e-170
Kurtosis:              8.276    Cond. No.                1.51e+04
=====

```

Warnings:

```

[1] Standard Errors assume that the covariance matrix of the errors is correctly
    specified.
[2] The condition number is large, 1.51e+04. This might indicate that there are
    strong multicollinearity or other numerical problems.

```

Principal component analysis

The initial dataset has a number of feature or predictor variables and one target variable to predict.

Principal component analysis (PCA) converts these features into a set of principal components, which are linearly uncorrelated variables.

The first principal component has the largest possible variance and therefore accounts for as much of the variability in the data as possible.

Each of the other principal components is orthogonal to all of its preceding components, but has the largest possible variance within that constraint.

Graphing a dataset by showing only the first two or three of the principal components effectively projects a complex dataset with high dimensionality into a simpler image that shows as much of the variance in the data as possible.

PCA is sensitive to the relative scaling of the original variables, so begin by scaling them:

```

# Feature Scaling
x = StandardScaler().fit_transform(X)

```

Calculate the first three principal components and show them for the first five rows of the housing dataset:

```


# Project data to 3 dimensions
pca = PCA(n_components=3)
principalComponents = pca.fit_transform(x)
principalDf = pd.DataFrame(
    data = principalComponents,
    columns = ['principal component 1', 'principal component 2', 'principal component
    3'])
principalDf.head()

```

row	principal component 1	principal component 2	principal component 3
0	-2.097842	0.777102	0.335076
1	-1.456412	0.588088	-0.701340
2	-2.074152	0.602185	0.161234
3	-2.611332	-0.005981	-0.101940
4	-2.457972	0.098860	-0.077893


Show a 2D graph of this data:

```
plt.scatter(principalDf['principal component 1'], principalDf['principal component 2
↪'], color='green')
plt.show()
```



Show a 3D graph of this data:

```
fig = plt.figure()
ax = fig.add_subplot(111, projection='3d')
ax.scatter(principalDf['principal component 1'], principalDf['principal component 2'],
↪ principalDf['principal component 3'])
plt.show()
```



Measure how much of the variance is explained by each of the three components:

```
# Variance explained by each component
explained_variance = pca.explained_variance_ratio_
explained_variance
```

```
array([0.47097344, 0.11015872, 0.09547408])
```

Each value will be less than or equal to the previous value, and each value will be in the range from 0 through 1.

The sum of these three values shows the fraction of the total variance explained by the three principal components, in the range from 0 (none) through 1 (all):

```
sum(explained_variance)
```


```
0.6766062376563704
```

Predict the target variable using only the three principal components:

```
y_test_linear = y_test
y_pred_linear = y_pred
X = principalDf
y = df['target']
X_train, X_test, y_train, y_test = train_test_split(X, y, test_size = 0.25, random_
↪state = 0)
regressor = LinearRegression()
regressor.fit(X_train, y_train)
y_pred = regressor.predict(X_test)
```

Plot the predictions from the linear regression in green again, and the new predictions in blue:

```
fig, ax = plt.subplots()
ax.scatter(y_test, y_pred, color='skyblue')
ax.scatter(y_test_linear, y_pred_linear, color = 'green')
ax.set(
    xlabel="Prices:  $Y_i$ ",
    ylabel="Predicted prices:  $\hat{Y}_i$ ",
    title="Prices vs Predicted prices:  $Y_i$  vs  $\hat{Y}_i$ ",
)
plt.show()
```



The blue points are somewhat more widely scattered, but similar.

Calculate the mean squared error:

```
print("Linear regression mean squared error: %.2f" % mean_squared_error(y_test_linear,
↪ y_pred_linear))
print("PCA mean squared error: %.2f" % mean_squared_error(y_test, y_pred))
```

```
Linear regression mean squared error: 29.79
PCA mean squared error: 43.49
```

3.6 Working with deployments

When you *deploy a project*, Anaconda Enterprise finds and builds all of the software dependencies—the libraries on which the project depends in order to run—and encapsulates them, so they are completely self-contained and easy to share with others. This is called a *deployment*.

Whether you deploy a notebook, Bokeh application or *REST API*, everything needed to deploy and run the project is included. You can then *share your deployment* with others so they can interact with it.

Note: You can create multiple deployments from a single project. Each deployment can be a different version, and can be shared with different users.

After logging in to Anaconda Enterprise, click **Deployments** to view a list of all of the deployments you have created—or that others have shared with you. Simply click on a deployment to open the deployed Notebook or application and interact with it.


Anaconda Enterprise maintains *a log of all deployments created by all users* in the Administrator’s Authentication Center.

3.6.1 Deploying a project

When you are ready to use your interactive visualization, live notebook or machine learning model, you *deploy* the associated project. You can also deploy someone else’s project if you have been added as a collaborator on the project. See *Collaborating on projects* for more information.

When you deploy a project, Anaconda Enterprise finds and builds the software dependencies—all of the libraries required for it to run—and encapsulates them so they are completely self-contained. This allows you to easily share it with others.

You configure how a project is deployed by adding the appropriate command to run the project in the configuration file `anaconda-project.yml`. You can also accept the default command, like the following example Bokeh app:



See *Configuring project settings* for more information about adding deployment commands to project.

To deploy a project:

1. Select it in the **Projects** list and click **Deploy**.

Create a Deployment from 'data_clustering' Project

Select from the following options to deploy this project. For more information on deployable projects, see documentation.

Name
data_clustering-1

Resource Profile
Default resource profile (CPU: 2, Memory: 4096Mi)

Version
0.1.0

Deployment Command
default (Bokeh app.)

☒ Static url
data-clustering-1 .product-mgmt.dev.anaconda.com

☐ Private

Cancel Deploy

2. Choose the runtime resources your project requires to run from the **Resource Profile** drop-down, or accept the default. Your Administrator configures the options in this list, so check with them if you aren't sure.
3. If there are multiple versions of the project, select the version you want to deploy.
4. Select the command to use to deploy the project. If there is no deployment command listed, you cannot deploy the project.


Return to the project and add a deployment command, or ask the project owner to do so if it's not your project. See [Configuring project settings](#) for more information about adding deployment commands.

5. Enter the URL where you want the deployment to be hosted in the **Static URL** field.

Note: This is the URL you'll use to call the deployment from within a web application, and therefore **it must be unique**. Disable the **Static URL** toggle if you want Anaconda Enterprise to automatically generate a URL for the deployment.


6. Choose whether you want to keep the deployment `Private`—and therefore accessible to authenticated platform users, only—or make it `Public`, and therefore available to non-authenticated users. After it's deployed, you can [share the deployment with others](#).
7. Click **Deploy**. Anaconda Enterprise displays the status of the deployment, then lists it in the project's **Deployments**. Private deployments are displayed with a lock icon next to their name, to indicate their secure status.

Note: It may take a few minutes to obtain and build all the dependencies for the project deployment.



Name	State	Project	Owner	Revision	Deployed	URL
gapminder_visualization	started	gapminder_visualization	cquinn	0.1.0	Aug 27, 2019, 2:07 PM	https://gapminder-visualization.product-mgmt.dev.anaconda.com/
data_clustering-1	started	data_clustering	anaconda-enterprise	0.1.0	Aug 26, 2019, 2:24 PM	https://data-clustering-1.product-mgmt.dev.anaconda.com/
data_clustering	started	data_clustering	anaconda-enterprise	0.1.0	Aug 26, 2019, 2:10 PM	https://data-clustering-product-mgmt.dev.anaconda.com/

To view or interact with a deployment, click its name in the list.



You can also schedule a project to be deployed on a regular basis or at a specific time.

3.6.2 Deploying a REST API

Anaconda Enterprise enables you to deploy your machine learning or predictive models as a REST API endpoint so others can query and consume results from them. REST APIs are web server endpoints, or callable URLs, which provide results based on a query, allowing developers to create applications that programmatically query and consume them via other user interfaces or applications.

Rather than sharing your model with other data scientists and having them run it, you can give them an endpoint to query the model, which you can continue to update, improve and redeploy as needed.

REST API endpoints deployed with Anaconda Enterprise are secure and only accessible to users that you've shared the deployment with or users that have generated a token that can be used to query the REST API endpoint outside of Anaconda Enterprise.

The process of deploying a REST API involves the following steps:

- *Create a project* to encapsulate all of the components necessary to use or run your model.
- *Deploy the project* with the `rest_api` command (shown in Step 4 below) to build the software dependencies—all of the libraries required for it to run—and encapsulate them so they are completely self-contained.

- *Share the deployment*, or the URL of the endpoint, and generate a unique token so that they can connect to the deployment and use it from within notebooks, APIs or other applications.

Using the API wrapper

As an alternative to using the REST API wrapper provided with Anaconda Enterprise, you can construct an API endpoint using any web framework and serve the endpoint on port 8086 within your deployment, to make it available as a secure REST API endpoint in Anaconda Enterprise.

Follow this process to wrap your code with an API:

1. Open the Jupyter Notebook and add this code to be able to handle HTTP requests. Define a global REQUEST JSON string that will be replaced on each invocation of the API.

```
import json
REQUEST = json.dumps({
    'path' : {},
    'args' : {},
    'body': {}
})
```

2. Import the Anaconda Enterprise publish function.

```
from anaconda_enterprise import publish
@publish(methods=['GET', 'POST'])
def function():
    ...
    return json.dumps(...)
```

3. Add the deployment command and an appropriate environment variable to the `anaconda-project.yml` file:

```
commands:
  deploy-api:
    rest_api: {notebook}.ipynb
    supports_http_options: true
    default: true

variables:
  KG_FORCE_KERNEL_NAME:
    default: python3
```

4. Ensure the `anaconda-enterprise` channel is listed under `channels:` and the `anaconda-enterprise-web-publisher` package is listed under `packages:`. For example:

```
packages:
- python=3.6
- pandas
- dask
- matplotlib
- scikit-learn
- requests
- anaconda-enterprise-web-publisher

channels:
- defaults
- anaconda-enterprise
```

5. Use the following command to test the API within your notebook session (without deploying it):

```
anaconda-project run deploy-api
```

6. Now if you visit `http://localhost:8888/{function}` from within a notebook session you will see the results of your function.

From within a notebook session, execute the following command:

```
curl localhost:8888/{function}
```

7. Click the **Deploy** icon in the toolbar to deploy the project as an API.

This deploys the notebook as an API which you can then query.

8. To query externally, create a token and find the url to the running project.

Example using `curl`:

```
export TOKEN="<generated-token-goes-here>" # save long string of text in variable
curl -L -H "Authorization: Bearer $TOKEN" <url-of-project>
```

The `-L` option tells `curl` to follow redirects. The `-H` adds a header. In this case `-H` adds the token required to authorize the client to visit that URL.

If you deploy the project as described above you can add the `-X POST` option to `curl` to access that function.

3.6.3 Deploying a Flask application

The process of deploying a Flask application (website and REST APIs) on Anaconda Enterprise involves the following:

1. Configuring Flask to *run behind a proxy*
2. Enabling Anaconda Project *HTTP command-line arguments*
3. Running Flask *on the deployed host and port*

Here is a small Flask application that includes the call to `.run()`. The file is saved to `server.py`.

This Flask application was written using `Blueprints`, which is useful for separating components when working with a large Flask application.

Here, the nested block in `if __name__ == '__main__':` could be in a separate file from the 'hello' Blueprint.

```
from flask import Flask, Blueprint

hello = Blueprint('hello', __name__)

@hello.route('/')
def hello_world():
    return 'Hello, World!'

if __name__ == '__main__':
    app = Flask(__name__)
    app.register_blueprint(hello, url_prefix='/')

    app.run()
```


Running behind an HTTPS proxy

Anaconda Enterprise maintains all HTTPS connections into and out of the server and deployed instances. When writing a Flask app, you only need to inform it that will be accessed from behind the proxy provided by Anaconda Enterprise.

The simplest way to do this is with the `ProxyFix` function from `werkzeug`. More information about proxies is provided [here](#).

```
from flask import Flask, Blueprint
from werkzeug.contrib.fixers import ProxyFix

hello = Blueprint('hello', __name__)

@hello.route('/')
def hello_world():
    return 'Hello, World!'

if __name__ == '__main__':
    app = Flask(__name__)
    app.register_blueprint(hello, url_prefix='/')

    app.wsgi_app = ProxyFix(app.wsgi_app)
    app.run()
```

Enabling command-line arguments

In your `anaconda-project.yml` file, you define a deployable command as follows:

```
commands:
  default:
    unix: python ${PROJECT_DIR}/server.py
    supports_http_options: true
```

The flag `supports_http_options` means that `server.py` is expected to act on the following command line arguments defined in the [Anaconda Project Reference](#).

This is easily accomplished by adding the following `argparse` code before calling `app.run()` in `server.py`

```
import sys
from argparse import ArgumentParser

# ... the Flask application blueprint

if __name__ == '__main__':
    # arg parser for the standard anaconda-project options
    parser = ArgumentParser(prog="hello_world",
                            description="Simple Flask Application")
    parser.add_argument('--anaconda-project-host', action='append', default=[],
                        help='Hostname to allow in requests')
    parser.add_argument('--anaconda-project-port', action='store', default=8086,
                        type=int,
                        help='Port to listen on')
    parser.add_argument('--anaconda-project-iframe-hosts',
                        action='append',
                        help='Space-separated hosts which can embed us in an iframe,
                        per our Content-Security-Policy')
```

(continues on next page)

(continued from previous page)

```

parser.add_argument('--anaconda-project-no-browser', action='store_true',
                    default=False,
                    help='Disable opening in a browser')
parser.add_argument('--anaconda-project-use-xheaders',
                    action='store_true',
                    default=False,
                    help='Trust X-headers from reverse proxy')
parser.add_argument('--anaconda-project-url-prefix', action='store', default='',
                    help='Prefix in front of urls')
parser.add_argument('--anaconda-project-address',
                    action='store',
                    default='0.0.0.0',
                    help='IP address the application should listen on.')

args = parser.parse_args()

```

Running your Flask application

The final step is to configure the Flask application with the Anaconda Project HTTP values and call `app.run()`. Note that registering the Blueprint provides a convenient way to deploy your application without having to rewrite the routes.

Here is the complete code for the Hello World application.

```

import sys
from flask import Flask, Blueprint
from argparse import ArgumentParser
from werkzeug.contrib.fixers import ProxyFix

hello = Blueprint('hello', __name__)

@hello.route('/')
def hello_world():
    return "Hello, World!"

if __name__ == '__main__':

    # arg parser for the standard anaconda-project options
    parser = ArgumentParser(prog="hello_world",
                           description="Simple Flask Application")
    parser.add_argument('--anaconda-project-host', action='append', default=[],
                        help='Hostname to allow in requests')
    parser.add_argument('--anaconda-project-port', action='store', default=8086,
                        type=int,
                        help='Port to listen on')
    parser.add_argument('--anaconda-project-iframe-hosts',
                        action='append',
                        help='Space-separated hosts which can embed us in an iframe_
↳per our Content-Security-Policy')
    parser.add_argument('--anaconda-project-no-browser', action='store_true',
                        default=False,
                        help='Disable opening in a browser')
    parser.add_argument('--anaconda-project-use-xheaders',
                        action='store_true',
                        default=False,

```

(continues on next page)

(continued from previous page)

```

        help='Trust X-headers from reverse proxy')
parser.add_argument('--anaconda-project-url-prefix', action='store', default='',
                    help='Prefix in front of urls')
parser.add_argument('--anaconda-project-address',
                    action='store',
                    default='0.0.0.0',
                    help='IP address the application should listen on.')

args = parser.parse_args()

app = Flask(__name__)
app.register_blueprint(hello, url_prefix = args.anaconda_project_url_prefix)

app.config['PREFERRED_URL_SCHEME'] = 'https'

app.wsgi_app = ProxyFix(app.wsgi_app)
app.run(host=args.anaconda_project_address, port=args.anaconda_project_port)

```

3.6.4 Sharing deployments

After you have *deployed a project*, you can *share* the deployment with others. You can share a deployment publicly, with other Anaconda Enterprise users, or both.

Any *collaborators* you add to your deployment will see your deployment in *their* **Deployments** list when they log in to AE.


Note: Your Anaconda Enterprise Administrator creates the users and groups with whom you can share your deployments, so check with them if you need a new group created.

To share a deployment:

1. If you're already working with the associated project, select **Deployments** in the left menu. Otherwise, click the top-level **Deployments** menu item to display all of your deployments.

Name	State	Project	Owner	Revision	Deployed	URL
tips.plot	failed	tips.plot	anaconda-enterprise	0.1.1	Aug 23, 2019, 4:18 PM	https://tipsplot.product-mgmt.dev.anaconda.com/
gapminder_visualization	shared	gapminder_visualization	cgunn	0.1.0	Aug 26, 2019, 2:45 PM	https://gapminder-visualization.product-mgmt.dev.anaconda.com/


2. Click the specific deployment you want to share and select **Share** in the left menu.




3. The deployment is `Public`, or accessible to any one who has the deployment URL, by default. You can copy and distribute the unique URL that's generated when you *deploy the project* to others with whom you want to share the deployment.

Note: If the deployment is going to be used as an endpoint that's called by other code (e.g., a REST API), you'll want to **provide a static URL** when *deploying the project*, and NOT use the generated URL displayed here. For more information, see *the instructions below*.

To limit access to the deployment to only those users with an access token, enable the `Public` toggle so it switches to `Private`.



4. To share the deployment with other users of the Anaconda Enterprise platform, start typing the name of the user or group in the **Collaborators** drop-down to search for matches. Select the one that corresponds to what you want, and click **Add**.




To remove collaborator access to a deployment, check the **X** next to the user or group you want to remove as collaborators and click **Remove** to confirm your selection.


To enable others to reference a deployment from within their code:

Rather than sharing your model with other data scientists and having them run it, you can give them an endpoint to query the model, which you can continue to update, improve and redeploy as needed.

Note: If the deployment is going to be used as an endpoint that's called by other code, you'll want to **provide a static URL** when *deploying the project*, and NOT use an auto-generated URL.

If your deployment is `Private`, you'll also need to *generate a token* that can be used to connect to the associated Notebooks, APIs or other running code. People will need both the deployment URL and the token to access a private deployment. **Tokens are powerful and should be protected like passwords.**

1. Click the deployment you want to generate a token for and select **Settings** in the left menu.
2. Scroll to the **Generate Tokens** setting and click **Generate**. Copy the token that's generated to the clipboard with the  icon, or by copying it with mouse or keyboard shortcuts like any other text.



You can then share this token, and the **Deployment URL**, with others to enable them to connect to the deployment from within Notebooks, APIs and other running code.

To remove a deployment from the server—thereby making it unavailable to yourself and others—you *terminate the deployment*. This also frees up its resources.


3.6.5 Scheduling deployments


If you want to *deploy a project* on a regular basis, Anaconda Enterprise enables you to schedule the deployment. For example, you can schedule a deployment that's resource intensive to run after regular business hours, or to import new data on a weekly basis.

Note: A task that's run via a scheduled deployment can read data previously committed to the project from an editor session, but cannot be used to commit any new data to it. Any data written to a scheduled deployment's container will

be deleted immediately after the scheduled task runs, so we recommend that you ensure data is read from and written to *external data sources*.

To schedule a deployment:

1. Open the project you want to schedule a deployment for by clicking on it in the **Projects** list.
2. Click **Schedules** in the menu on the left.
3. Click **Create a Schedule** if it's the first schedule to be created for the project, or the Schedule  button if there are existing schedules.



4. Give the schedule a meaningful name to help differentiate it from any other schedules.
5. Specify whether you want to deploy the latest version of the project, or select a particular version.
6. Specify the **Deployment Command** to use to deploy the project. Schedules are intended for automatic or non-interactive execution of script files or notebooks, therefore only `unix:` commands are supported. See an example [here](#).


Note: If there is no deployment command listed, you cannot deploy the project. Return to the project and add a deployment command, or ask the project owner to do so if it's not your project. See [Configuring project settings](#) for more information about adding deployment commands.

7. Choose the runtime resources your project requires to run from the **Resource Profile** drop-down, or accept the default. Your Administrator configures the options in this list, so check with them if you aren't sure.
8. Use the controls to specify how often and when you want to schedule the deployment, or select **Custom** and enter a valid [cron expression](#). To help ensure your schedule runs when you intend it to, we recommend you [verify your cron expression](#) before saving your schedule.


Note: All scheduled times are in UTC (Coordinated Universal Time).

Alternatively, if you want it to run *now*—instead of scheduling it—select **Run Now**.

9. Click **Schedule** to create the schedule, and display it in the list of schedules for the project.



10. Click on a schedule in the list to view and edit its details.




11. Use the controls above the schedule to pause, edit, or delete a selected schedule.

Note: If you attempt to delete a schedule that is currently running or is scheduled to run, you will be prompted to confirm that you want to force the deletion.

To view a list of all the scheduled deployments that are currently running or have already run, click **Runs** in the menu on the left.

Select a specific run in the list to enable the controls to refresh, stop or delete it.




3.6.6 Terminating a deployment


When a deployment is no longer required, you can terminate it to stop it from running. This will remove it from the server and free up the resources it's currently using. Terminating a deployment does not affect the original *project* from which the deployment was created—only the deployment. It does make the deployment unavailable to *any users you had shared it with*, however.

To terminate a deployment:

1. Click the top-level **Deployments** menu item to display all of your deployments.



2. Click the specific deployment you want to terminate, and click **Settings** in the menu on the left.




3. Scroll down until the **Terminate** button is visible, and click it.
4. Confirm that you want to stop the deployment. The deployment stops, and is removed from the list of deployments.

3.7 Using GPUs in sessions and deployments

Anaconda Enterprise enables you to leverage the compute power of graphics processing units (GPUs) from within your editor sessions. To do so, you can select a resource profile that features a GPU when you first create the project, or use the project's **Settings** tab to select a resource profile after the project is created.


To enable access to a GPU while running a *deployed application*, select the appropriate resource profile when you *deploy the associated project*.

In either case, if the resource profile you need isn't listed, ask your Administrator to *configure one for you to use*.



3.8 Configuring your user settings

Anaconda Enterprise maintains settings related to your user account, based on how the system was configured by your Administrator. There are times when you may need to update the information related to your user account—to change your password, *add credentials required to access a version control repository*, or *add secrets* that can be used to access file systems, data stores and other resources implemented by your organization, for example.

To access your account settings, click the **User** icon  in the upper-right corner and select the **Settings** option in the pull-down.

Click **Advanced Settings** to configure the following settings for your Anaconda Enterprise account:

- To change the email or name associated with your account, edit the associated field for the **Account**.
- To change the password you use to log in to Anaconda Enterprise, select **Password**.
- To enable two-factor authentication for your account, select **Authenticator**.
- To view a history of your sessions using Anaconda Enterprise, select **Sessions**. You can also log out of all sessions in one click [here](#).
- To view a list of AE applications currently running and the permissions you have been granted, select **Applications**.
- To view a log of all activity related to your account, select **Log**.

Note: Fields that you are not permitted to edit appear grayed / disabled.

3.8.1 Configuring access to version control

If your Administrator has configured Anaconda Enterprise to use a supported version control repository other than the internal GitHub server, you'll need to provide your credentials to be able to access that repository. *We recommend you create an ever-lasting token, so you can retain permanent access to your files from within Anaconda Enterprise.*

Your auth token must also have the following permissions:

External Repository	Permissions Required
Bitbucket Enterprise	Admin access for Projects and Repositories
GitHub Enterprise	<code>repo:status</code> , <code>repo_deployment</code> , <code>public_repo</code> , <code>repo:invite</code> , and <code>delete_repo</code>
GitLab Enterprise	Check the <code>api</code> access check box when creating your access token.

Note: You'll be prompted to configure your personal access token when you attempt to create your first project in Anaconda Enterprise, if you haven't already done so.

1. Under **External Version Control Credentials**, click **Add**.

2. Enter the username and personal access token you use to access the repository in the relevant fields.
3. Click **Add** to update the platform with your credentials.

To manage credentials that you've added, click on the command menu  for the credentials, then choose whether you want to edit or delete them.

Now that you've configured access, you'll be able access the repository within your sessions and deployments without having to leave the platform. Anaconda Enterprise creates a repository for each *project that you create*.

3.8.2 Storing secrets


Anaconda Enterprise enables you to securely store information such as user names, passwords, API keys, or authentication tokens. Any secrets you add will be available across sessions and deployments for all projects associated with your account—but the values are not shared with other users.

Secrets are mounted into deployments and sessions as files, where the name of the file matches the name of the secret. Each file stores the value provided for that secret. You can access the contents of these files from within your projects, to access file systems, data stores and other resources implemented by your organization.

Note: We highly recommend you use the secrets store over including credentials in your project, due to the potential security risk associated with storing them in version control.

1. Under **Secrets**, click **Add**.
2. Enter a **Name** and **Value** for the secrets you want to store, then click **Add**.

Note: Secret names can contain alphanumeric characters and underscores only—not special characters or paths.

Any secrets you add are listed by name. To manage your secrets, click on the command menu  for the item then choose whether you want to edit, delete or copy the name of the secret.

To access credentials you've added within a session, deployment, or scheduled job:

1. Open a new terminal window.
2. Change directory to the location where the secrets are stored: `/var/run/secrets/user_credentials/`.
3. Run `cat <credential_key>`—replacing `credential_key` with the actual key name—to display the value you entered when you added the secret.
4. Use the value to access the file system, data store or other resource as needed. See [Loading data](#) for more information.


3.9 Visualizations and dashboards


Anaconda Enterprise makes it easy for you to create and share interactive data visualizations, live notebooks or machine learning models built using popular libraries such as Bokeh and HoloViews.

To get you started quickly, Anaconda Enterprise provides sample projects of Bokeh applications for clustering and cross filtering data. There are also several [examples of AE5 projects that use PyViz here](#).


Follow these steps to create an interactive plot:

1. From the **Projects** view, select **Create + > New Project** and create a project from the Anaconda 3.6 (v5.0.1) template:



2. Open the project in a session , select **New > Terminal** to open a terminal, and run the following command to install packages for hvplot, panel, pyct, and bokeh:

```
anaconda-project add-packages hvplot panel
```



3. Select **New > Python 3** to create a new notebook, rename it `tips.ipynb`, and add the following code to create an interactive plot:

```
import pandas as pd
import hvplot.pandas
import panel

panel.extension()


df = pd.read_csv('http://bit.ly/tips-csv')
p = df.hvplot.scatter(x='total_bill', y='tip', hover_cols=['sex', 'day', 'size'])
pn.Pane(p).servable()
```

Note: In this example, the data is being read from the Internet. Alternatively, you could [download](#) the `.csv` and upload it to the project.

4. Open the project's `anaconda-project.yml` file, and add the following lines after the description. This is the deployment command that Anaconda Enterprise will use when you deploy the notebook

```
commands:
  scatter-plot:
    unix: panel serve tips.ipynb
    supports_http_options: True
```

5. Save and commit your changes.



6. Now you're ready to deploy the project.

Commit Changes

Local (mine) 2 files staged

<input checked="" type="checkbox"/>	File	Modified	Type
<input checked="" type="checkbox"/>	tips.ipynb	7/29/19, 4:23 PM	unversioned
<input checked="" type="checkbox"/>	anaconda-project.yml	7/29/19, 4:06 PM	modified

Master

No changes from 'master'

Commit Message

new notebook

Tag

0.1.1

Latest version

0.1.0

Used to help create a deployable

Cancel Commit

Create a Deployment from 'tips.plot' Project

Select from the following options to deploy this project. For more information on deployable projects, see documentation.

Name

tips.plot

Resource Profile

Default resource profile (CPU: 2, Memory: 4096Mi)

Version

0.1.1

Deployment Command

scatter-plot (panel) serve (tips.ipynb)

Static url

tipsplot

product-mgmt.dev.anaconda.com

Private

Cancel Deploy

You can also share the deployment with others.

3.10 Machine learning and deep learning

Anaconda Enterprise facilitates machine learning and deep learning by enabling you to *develop models*, *train them*, and *deploy them*. You can also use AE to *query and score models* that have been *deployed as a REST API*.

To help get you started, Anaconda Enterprise includes several sample notebooks for common repetitive tasks. You can access them from the gallery of Sample Projects available from **Projects**. See *Working with projects* for more information.

We've also provided a walkthrough of the process for creating an interactive data visualization.

3.10.1 Developing models

Anaconda Enterprise makes it easy for you to create models that you can *train* to make predictions and facilitate machine learning based on deep learning neural networks.

You can *deploy* your trained model as a REST API, so that it can be *queried and scored*.

The following libraries are available in Anaconda Enterprise to help you develop models:

- **Scikit-learn**—for algorithms and model training.
- **TensorFlow**—to express numerical computations as stateful dataflow graphs.
- **XGBoost**—a gradient boosting framework for C++, Java, Python, R and Julia.
- **Theano**—expresses numerical computations & compiles them to run on CPUs or GPUs.
- **Keras**—contains implementations of commonly used neural network building blocks to make working with image and text data easier.
- **Lasagne**—contains recipes for building and training neural networks in Theano.
- **Neon**—deep learning framework for building models using Python, with Math Kernel Library (MKL) support.
- **MXNet**—framework for training and deploying deep neural networks.
- **Caffe**—deep learning framework with a Python interface geared towards image classification and segmentation.
- **CNTK**—cognitive toolkit for working with massive datasets to facilitate distributed deep learning. Describes neural networks as a series of computational steps via a directed graph.

3.10.2 Training models

Anaconda Enterprise provides machine learning libraries such as scikit-learn and Tensorflow that you can use to train the models you create.

To train a model:

When you are ready to run an algorithm against your model and tune it, download the `scikit-learn` or `Tensorflow` package from the `anaconda` channel. If you don't see this channel or these packages in your **Channels** list, contact your Administrator to *mirror these packages* to make them available to you.

Serializing your model:

When you are ready to convert your model or application into a format that can be easily distributed and reconstructed by others, use Anaconda Enterprise to *deploy it*.

- YAML – supports non-hierarchical data structures & scalar data
- JSON – for client-server communication in web apps
- HD5 – designed to store large amounts of hierarchical data; works well for time series data (stored in arrays)

Note: Your model or app must be written in a programming language that supports object serialization, such as Python, PHP, R or Java.

3.10.3 Deploying models as endpoints

Anaconda Enterprise enables you to deploy machine learning models as endpoints to make them available to others, so the models can be *queried and scored*. You can then save users’ input data as part of the training data, and retrain the model with the new training dataset.

Versioning your model:

To enable you to test variations of a model, you can *deploy multiple versions of the model*. You can then direct different sets of users to each of the versions, to facilitate A/B testing.

Deploying your model as an endpoint:

Deploying a model as an endpoint involves these simple steps:

1. *Create a project* to tell Anaconda Enterprise where to look for the artifacts that comprise the model.
2. *Deploy the project* to build the model and all of its dependencies. Now you—and others with whom you *share the deployment*—can interact with the app, and select different datasets and algorithms.

3.10.4 Querying and scoring models

Anaconda Enterprise enables you to query and score models that have been created in Python, R, or another language such as Curl, CLI, Java or Javascript. The model doesn’t have to have been created using AE, as long as the model has been *deployed as an endpoint*.

Scoring can be incredibly useful to an organization, including the following “real world” examples:

- By financial institutions, to determine the level of risk that a loan applicant represents.
- By debt collectors, to predict the likelihood of a debtor to repay their debt.
- By marketers, to predict the likelihood of a subscriber list member to respond to a campaign.
- By retailers, to determine the probability of a customer to purchase a product.

A scoring engine calculates predictions or makes recommendations based on your model. A model’s score is computed based on the model and query operators used:

- Boolean queries—specify a formula
- Vector space queries—support free text queries (with no query operators necessarily connecting them)
- Wildcard queries—match any pattern

Using an external scoring engine


Advanced scoring techniques used in machine learning algorithms can automatically update models with new data gathered. If you have an external scoring engine that you prefer to use on your models, you can do so within Anaconda Enterprise.

Anaconda Enterprise provides detailed logs and monitoring information related to the Kubernetes services and containers it uses. You can use the Operations Center and Kubernetes CLI to access this information, to help diagnose and debug errors that you or other users may encounter while using the platform.

4.1 The Anaconda Enterprise cluster

As an Operations Center Admin, you can use the Operations Center to configure and monitor the platform.


To access the Operations Center:

1. Log in to Anaconda Enterprise, select the **Menu** icon  in the top right corner, and click the **Administrative Console** link displayed at the bottom of the slide out window.
2. Click **Manage Resources**.
3. Login to the Operations Center using the Administrator credentials *configured after installation*.


To view resource utilization:

1. Select **Servers** in the menu on the left.
2. Click on the Private IP address of the Anaconda Enterprise master node, and select **SSH login as root**.

3. To display the current resource utilization of each *node* in the cluster, run this command:




```
kubectl top nodes --heapster-namespace=monitoring
```



Note: This is actual resource utilization, not limits or requests.


- To view utilization *and requests* for a particular node, run the `kubectl describe node` command against the IP address for the node (listed under NAME). For example:

```
kubectl describe node 172.31.25.175
```




5. To view the resource utilization per *pod*, run this command:

```
kubectl top pods --heapster-namespace=monitoring
```



6. To view the current status of all pods in the cluster, run `kubectl get pods`.




The following table summarizes common pod states:

Status	Description
Running	The pod has been bound to a node, and at least one container is running.
Pending	The pod is waiting for one or more container images to be created.
Terminating	The pod is in the process of being terminated.
Error	An error has occurred with the pod.
Init:CrashLoopBackoff	The pod failed to start, and will make another attempt in a few minutes.

7. To view information for a particular pod, run the `kubectl describe pod` command against the pod (listed under NAME). For example:

```
kubectl describe pod anaconda-session-89747d7fdb154b89b182d5eaa25b2e59-7f497db55w19g
```




```

Name: manual-testing-dev-anaconda.com/platform/storage/api/v1/projects/4be92a184678435d33d3c10e233806
Namespace: manual-testing-dev-anaconda.com/platform/storage/api/v1/projects/4be92a184678435d33d3c10e233806
Node: 172.17.0.176
Start Time: Thu, 06 Jun 2019 15:54:09 +0000
Labels: pod=manual-testing-dev-anaconda.com/platform/storage/api/v1/projects/4be92a184678435d33d3c10e233806
Annotations: kubernetes.io/ps=manual-testing-dev-anaconda.com/platform/storage/api/v1/projects/4be92a184678435d33d3c10e233806
Status: Running
IP: 10.244.1.12
Controlled By: ReplicaSet/anaconda-session-89747d7f7db154d89b182d5ea23b2e59-7f497db35w1g
Container ID: docker://84e7d3c76d61d3a864e738a61e23889c836bb6791154f4e28
Image: leader:telekube-local:19000/ae-editor:3.3.3-33-80484c7384
Image ID: docker-pull://leader:telekube-local:19000/ae-editor:3.3.3-33-80484c7384
Port: 7808/TCP
Host Port: 7808/TCP
State: Running
Started: Thu, 06 Jun 2019 15:54:04 +0000
Ready: True
Restart Count: 0
Limits:
  CPU: 2
  memory: 4Gi
  requests:
    CPU: 8
    memory: 8
  requests:
    CPU: 5m
    memory: 28Mi
  requests:
    CPU: 8
    memory: 8
Environment:
  TOOL_ID: 25429185864f4811b112946477c89b
  TOOL_IP: 89747d7f7db154d89b182d5ea23b2e59.manual-testing-dev.anaconda.com
  TOOL_PORT: 7808
  TOOL_PROJECT_URL: https://manual-testing-dev.anaconda.com/platform/storage/api/v1/projects/4be92a184678435d
  TOOL_PROJECT_BRANCH: manual-testing-dev-anaconda-enterprise-1204b3f6d6e54f9794f38aef8242f046
  TOOL_PACKAGE: notebook
  
```

You can also use the Operations Center **Logs** to gain insights into pod behavior and troubleshoot issues. See logging for more information.


4.2 User errors

If a user experiences issues within a Notebook session, have them send you the name of the pod associated with their project session. They can obtain this information by running the `hostname` command from within a Jupyter Notebook or terminal window.



```


In [1]: !hostname
anaconda-session-0f34e6b2d75144b6b6422243f468b37a-865bf58ftwtc
  
```



```


(lab_launch) hostname
anaconda-session-0f34e6b2d75144b6b6422243f468b37a-865bf58ftwtc
(lab_launch)
  
```


You can then use the commands described above or the Operation Center's **Monitoring** and **Logs** features to investigate the issue. See [Monitoring sessions and deployments](#) for more information.



Tip: As an Administrator, you can also use the Authentication Center to impersonate a user to try to reproduce the problem they are experiencing.

To access the Authentication Center:

1. Login to Anaconda Enterprise, click the **Menu** icon  in the top right corner, then click the **Administrative Console** link in the bottom of the slideout menu.
2. Click **Manage Users**.
3. In the Manage menu on the left, click **Users**.
4. On the **Lookup** tab, click **View all users** to list every user in the system, or search the user database for all users that match the criteria you enter, based on their first name, last name, or email address.
5. Click **Impersonate** in the row of **Actions** for the user to display a table of all **Applications** this user has interacted with on the platform, including editor sessions and deployments.
6. Click the **Anaconda Platform** link to interact with Anaconda Enterprise as the user.



Application	Available Roles	Granted Permissions	Additional Grants	Action
Account	Offline access, Manage account in Account, View profile in Account	Full Access		
my client	Offline access	Full Access		
Broker	Offline access	Full Access		
Anaconda Workspace Proxy	Anaconda Enterprise project deployer, Obtain permissions, Anaconda Enterprise package uploader, Anaconda Enterprise project creator, Offline access, Manage account in Account, View profile in Account	Full Access		
Anaconda Platform	Anaconda Enterprise project deployer, Obtain permissions, Anaconda Enterprise package uploader, Anaconda Enterprise project creator, Offline access, Manage account in Account, View profile in Account	Full Access	Offline Token	Revoke Grant
session_client_80747d7db154b89b18255ea25b2d59	Offline access	Full Access		
Anaconda Enterprise Notebooks	Anaconda Enterprise project deployer, Obtain permissions, Anaconda Enterprise	Full Access		

See Managing users for more information on managing users.

4.3 Editor sessions

To help you troubleshoot issues with editor sessions, it might be helpful to understand what is happening “behind the scenes”.

- When a user starts a session, Anaconda Enterprise launches the appropriate editor for them to work with their project files. In the background, the editor environment and other services are running in Docker containers.
- To improve startup time for projects, the editor container includes conda environments for each of the *project template environments* provided by the platform. These environments are stored in `/opt/continuum/anaconda/envs`, along with any custom environments created *during the editor session*.
- The project repository is cloned into `/opt/continuum/project`. (Only changes to files in this directory can be saved to the repository.)
- The `anaconda-project prepare` command runs, scans the project’s `anaconda-project.yml` file for new packages and environments, and installs them into the running session.

During this phase, you can monitor the progress by watching the output of `/opt/continuum/preparing`.

When this process completes, the `/opt/continuum/prepare.log` is created.

Warning: Any changes made to the container image will be lost when the session stops, so any packages installed from the command line are available during the current session only. To persist package installs across sessions, they must be added to the project’s `anaconda-project.yml` file.

Reference materials

The following information is provided for your reference, to help you understand some of the core terminology used in Anaconda Enterprise, and what changes were made between releases.

We also include answers to common questions you may have, and workarounds for known issues you may encounter while using the platform.

Additional information to help you get the most out of Anaconda features is available at <https://support.anaconda.com/>.

5.1 Glossary

Anaconda

Sometimes used as shorthand for the Anaconda Distribution, Anaconda, Inc. is the company behind Anaconda Distribution, conda, conda-build and Anaconda Enterprise.

Anaconda Cloud

A cloud package repository hosting service at <https://www.anaconda.org>. With a free account, you can publish packages you create to be used publicly.

Anaconda Distribution

Open source repository of hundreds of popular data science packages, along with the conda package and virtual environment manager for Windows, Linux, and MacOS. Conda makes it quick and easy to install, run, and upgrade complex data science and machine learning environments like scikit-learn, TensorFlow, and SciPy.

Anaconda Enterprise

A software platform for developing, governing, and automating data science and AI pipelines from laptop to production. Enterprise enables collaboration between teams of thousands of data scientists running large-scale model deployments on high-performance production clusters.

Anaconda Navigator

A desktop Graphical User Interface (GUI) included in Anaconda Distribution that allows you to easily use and manage IDEs, conda packages, environments, channels, and notebooks without the need to use the Command Line Interface (CLI).

Anaconda project

An encapsulation of your data science assets to make them easily portable. Projects may include files, environment variables, runnable commands, services, packages, channels, environment specifications, scripts, and notebooks. Each project also includes an `anaconda-project.yml` configuration file to automate setup, so you can easily run and share it with others. You can create and configure projects from the Enterprise web interface or command line interface.

Channel

A location in the repository where Anaconda Enterprise looks for packages. Enterprise Administrators and users can define channels, determine which packages are available in a channel, and restrict access to specific users or groups.

Commit

To make a set of local changes permanent by copying them to the remote server. Anaconda Enterprise checks to see if your work will conflict with any commits that your colleagues have made on the same project, so the files will not be overwritten unless you so choose to do so.

Conda

An open source package and environment manager that makes it quick and easy to install, run, and upgrade complex data science and machine learning environments like scikit-learn, TensorFlow, and SciPy. Thousands of Python and R packages can be installed with conda on Windows, MacOS X, Linux and IBM Power.

Conda-build

A tool used to build conda packages from recipes.

Conda environment

A superset of Python virtual environments, conda environments make it easy to create projects with different versions of Python and avoid issues related to dependencies and version requirements. A conda environment maintains its own files, directories, and paths so that you can work with specific versions of libraries and/or Python itself without affecting other Python projects.

Conda package

A binary tarball file containing system-level libraries, Python and R modules, executable programs, or other components. Conda tracks dependencies between specific packages and platforms, making it simple to create operating system-specific environments using different combinations of packages.

Conda recipe

Instructions used to tell conda-build how to build a package.

Deployment

A deployed Anaconda project containing a Notebook, web app, dashboard or machine learning model (exposed via an API). When you deploy a project, Anaconda Enterprise builds a container with all the required dependencies and runtime components—the libraries on which the project depends in order to run—and launches it with the security and access permissions defined by the user. This allows you to easily run and share the application with others.

Interactive data application

Visualizations with sliders, drop-downs and other widgets that allow users to interact with them. Interactive data applications can drive new computations, update plots and connect to other programmatic functionality.

Interactive development environment (IDE)

A suite of software tools that combines everything a developer needs to write and test software. It typically includes a code editor, a compiler or interpreter, and a debugger that the developer accesses through a single Graphical User Interface (GUI). An IDE may be installed locally, or it may be included as part of one or more existing and compatible applications accessed through a web browser.

Jupyter

A popular open source IDE for building interactive Notebooks by the Jupyter Foundation.

JupyterHub

An open source system for hosting multiple Jupyter Notebooks in a centralized location.

JupyterLab

Jupyter Foundation's successor IDE to Jupyter, with flexible building blocks for interactive and collaborative computing. For Jupyter Notebook users, the interface for JupyterLab is familiar and still contains the notebook, file browser, text editor, terminal, and outputs.

Jupyter Notebook

The default browser-based IDE available in Anaconda Enterprise. It combines the notebook, file browser, text editor, terminal and outputs.

Live notebook

JupyterLab and Jupyter Notebooks are web-based IDE applications that allow you to create and share documents that contain live code in R or Python, equations, visualizations, and explanatory text.

Package

Software files and information about the software—such as its name, description, and specific version—bundled into a file that can be installed and managed by a package manager. Packages can be encapsulated into Anaconda projects for easy portability.

Project template

Contains all the base files and components to support a particular programming environment. For example, a Python Spark project template contains everything you need to write Python code that connects to Spark clusters. When creating a new project, you can select a template that contains a set of packages and their dependencies.

Repository

Any storage location from which software or software assets may be retrieved and installed on a local computer.

REST API

A common way to operationalize a machine learning model is through a REST API. A REST API is a web server endpoint, or callable URL, which provides results based on a query. REST APIs allow developers to create applications that incorporate machine learning and prediction, without having to write models themselves.

Session

An open project, running in an editor or IDE.

Spark

A distributed SQL database and project of the Apache Foundation. While Spark has historically been tightly associated with Apache Hadoop and run on Hadoop clusters, recently the Spark project has sought to separate itself from Hadoop

by releasing support for Spark on Kubernetes. The core data structure in Spark is the RDD (Resilient Distributed Dataset)—a collection of data types, distributed in redundant fashion across many systems. To improve performance, RDDs are cached in memory by default, but can also be written to disk for persistence. Spark Ignite is a project to offer Spark RDDs that can be shared in-memory across applications.

5.2 Release notes

The following notes are provided to help you understand the major changes made between releases, and therefore may not include minor bug fixes and updates. If you are experiencing issues using Anaconda Enterprise, consider *reviewing the known issues documented here* to find workarounds.

5.2.1 Anaconda Enterprise 5.4.1

Released: April 15, 2020

Administrator-facing changes

- Updated *minimum and recommended requirements*
- You can now **configure size limits for files** (Default value of 50MB) being committed into the internal git by changing the related values on the *config map flag*. This ensures that projects don't get bogged down by oversized internal storage. We recommend keeping files below 50MB and using external file storage for large data sets. (AENT-5922)
- You can now **set the number of max concurrent queue jobs** and **enable/disable project creation** with a queue using a *config map flag*. By implementing a queue, Kubernetes jobs for project creation are performed only when resources are available, ensuring that project creation doesn't fail due to lack of cluster resources. (AENT-5801)
- Default **SSO Timeout increased** to 1 day.

User-facing changes

- You now have the ability to **see whether your project is in the queue** or actively being created.
- You will now be **alerted when your commits fail**, saving time and work.
- You can now **schedule your deployment in multiple timezones** via a dropdown in the Scheduler UI. Note that these scheduled deployment times will be displayed in UTC.
- You can now **access public channels and deployments** if not added as collaborators.
- **CRON string validation** has been added to schedules UI.

Backend improvements (non-visible changes)

- There was an issue with users trying to create multiple projects at a time, overwhelming the cluster resources and ultimately causing some projects to fail to create. We've fixed that by **implementing a job queue**, limiting the number of simultaneous project creations based on configuration and available system resources.
- GPU support fixed, **built on CUDA 10.x**.
- Job pods **automatically clean up** upon completion of jobs.

5.2.2 Anaconda Enterprise 5.4.0

Released: October 31, 2019

Administrator-facing changes

- Updated *minimum and recommended requirements*
- Added support for installing the Anaconda Enterprise cluster on *Centos/RHEL 7.7, 8.0*
- Upgraded Gravity to version 6.1.9 (and Kubernetes 1.15.05) with updated *monitoring dashboards*
- Ability to configure external Postgres database
- Authenticated NFS mounts
- Customize Sample Gallery and new project template collection. Requires *AE5 Tools*.

User-facing changes

- New UI look-and-feel
- New sample gallery projects
- Fixed JupyterLab and Jupyter Notebook timeout
- Upgraded Conda to version 4.6.14 and anaconda-project to version 0.8.3. Provide faster package installs and improved error messages
- NFS mounts now work with scheduled jobs

Backend improvements (non-visible changes)

- Upgraded nginx to version 1.17.2, which uses nginx-ingress version 1.5.2, to address CVEs.

5.2.3 Anaconda Enterprise 5.3.1

Released: July 17, 2019

Administrator-facing changes

- Added support for using *on-premises versions of Bitbucket and GitLab*, and removed the previous requirement to connect to your repository endpoint over SSL.
- Added support for installing the Anaconda Enterprise cluster on *RHEL/CentOS 7.6*.
- Added support for NVIDIA CUDA 10.0 drivers on *GPU worker nodes*.
- Added the ability to *set global environment variables via a new configuration file*, making them available across all containers. This method can be used to *address the issue* where values in custom `.condarc` files could be overwritten if the file was placed in a directory of “lower priority” than the user’s home directory.

User-facing changes

- Patched JupyterLab and Jupyter Notebook to address “session timeout” and “failed to fetch” issues. Users may still see an error, but if they reload their notebook, they can continue working without losing any work.
- Fixed issue where users were being asked to confirm the environment when creating a project from the Hadoop-Spark template.
- Fixed issue where the UI makes it appear that changes made by collaborators on a project have not been committed, when they have been, leading the user to believe that an error has occurred.
- Improved the usability of the *Schedules UI*.

Backend improvements (non-visible changes)

- Upgraded Jupyter Notebook to version 5.7.8 to address CVEs.
-

5.2.4 Anaconda Enterprise 5.3.0

Released: March 22, 2019

Administrator-facing changes

- Increased the *minimum and recommended disk space requirements* for the master node.
- Added recommendation to setup partitions on the master node using Logical Volume Management (LVM) to accommodate easier future expansion.
- Added `noarch` to the default platforms in the `anaconda.yaml` mirror *config file*.
- Added a bootstrap executable that you can run to *install conda* to the Anaconda Enterprise installer.
- Changed the process for *installing and configuring the Anaconda Enterprise cli and cas-mirror* slightly.

User-facing changes

- Added ability to *deploy projects* to user-supplied, static URLs.
 - Improved UI notifications on behind-the-scenes processes, and added a Notification Center.
 - Optimized database operations and made other performance improvements.
 - Added a sample project for connecting to an S3 bucket.
 - Fixed issue where users couldn't use Kerberos authentication (kinit) to access a Spark/Hadoop cluster from within a notebook.
 - Fixed issue where incorrect default kernels were being used for projects created from the Hadoop-Spark template.
 - Improved error message handling to clarify errors and provide instructions on how to workaround or recover from them.
 - Added usability improvements related to scheduling deployment runs, audit trail logging, and session initialization.
-

5.2.5 Anaconda Enterprise 5.2.4

Released: January 21, 2019

Administrator-facing changes

- Fixed issue where custom resource profiles weren't being captured during in-place upgrades.
 - Added security fixes.
-

5.2.6 Anaconda Enterprise 5.2.3

Released: January 2, 2019

- Included fix to address a vulnerability in Kubernetes which allowed for permission escalation. You can learn more about the vulnerability [here](#).

User-facing changes

- Added ability for users to store secrets that can be used to access file systems, data stores and other enterprise resources from within sessions and deployments. Any secrets added to the platform will be available across all projects associated with the user's account. For more information, see *Storing secrets*.
 - Fixed issue that required users to modify the `anaconda-project.yml` file to make the Hadoop-Spark environment template work properly.
 - Added ability to view each project's owner, and sort the list of projects based on this column.
 - Fixed various issues to improve project and session performance.
-

5.2.7 Anaconda Enterprise 5.2.2

Released: October 10, 2018

Administrator-facing changes

- Added ability to configure an external Git repository (instead of the internal Git repository) to store projects containing version-controlled notebooks, code, and other files. Supported external Git version control systems include Atlassian BitBucket, GitHub and GitHub Enterprise, and GitLab.
- Administrators can optionally configure GPU worker nodes to be used only for sessions and deployments that require a GPU (by preventing CPU-only sessions and deployments from accessing GPU resources).
- In-place upgrades can now be performed from AE 5.2.x to AE 5.2.2.
- Improved functionality in backup script related to backup location and disk capacity requirements.
- Implemented multiple security enhancements related to cache control headers, HTTP strict transport security, and default ciphers and protocols across all services.
- Administrators no longer need to generate separate TLS/SSL certificates for the Operations Center.
- Improved validation of custom TLS/SSL certificates in the Administrator Console.
- Administrators can now disable access to `sudo yum` operations in sessions across the platform.
- Fixed an issue related to orphaned clients for sessions and deployments not being removed from Authentication Center.
- Tokens for user notebook sessions and deployments are now stored in encrypted format.
- Renamed platform-wide conda settings to `default_channels`, `channel_alias`, `ssl_verify` settings in the `conda` section of configmap to be consistent with conda configuration settings.
- Administrators can now specify the channel priority order when creating environments/installers.
- Fixed an issue related to sorting of package versions when creating environments/installers.
- Fixed an issue with download links for custom Anaconda parcels.
- Improved behavior of package mirroring tool to only remove existing packages when clean mode is active.
- Fixed an issue related to mirroring pip packages from PyPI repository.

- Added support for `noarch` packages in package mirroring tool.
- Improved logging and error handling in package mirroring tool.
- Fixed an issue related to projects failing to be created due to special characters in usernames.
- Fixed an issue related to authorization center errors when syncing large number of users from external identity providers.
- Added logout functionality to `anaconda-enterprise-cli`.

User-facing changes

- Apache Zeppelin is now available as a notebook editor for projects (in addition to Jupyter Notebooks and JupyterLab). Apache Zeppelin is a web-based notebook that enables data-driven, interactive data analytics and collaborative documents with interpreters for Python, R, Spark, Hive, HDFS, SQL, and more.
- Conda channels in the repository can be made publicly available (default), or access can be restricted to specific authenticated users or groups.
- A single notebook kernel (associated with the active conda environment used within a project) is now displayed by default in Jupyter Notebooks and JupyterLab.
- Collaborators can now select a different default editor for projects that have been shared with them.
- Implemented various fixes to configuration parameters for scheduled jobs within a project.
- Improved input/form validation related to projects, deployments, packages, and settings across the platform.
- Improved error messaging/handling across the platform, along with the ability to view errors and logs from underlying services.
- Improved notifications for tasks such as uploading projects and copying sample projects.
- Users are now prompted to delete all related sessions, deployments, jobs, and runs (including those used by collaborators) when deleting a project.
- Fixed an issue that caused numerous erroneous job runs to be spawned based on the default job scheduling parameters.

5.2.8 Anaconda Enterprise 5.2.1

Released: August 30, 2018

User-facing changes

- Fixed issue with loading spinner appearing on top of notebook sessions
- Fixed issue related to missing projects and copying sample projects when upgrading from AE 5.1.x
- Improved visual feedback when loading notebook sessions/deployments and performing actions such as creating/copying projects

5.2.9 Anaconda Enterprise 5.2.0

Released: July 27, 2018

Administrator-facing changes

- New administrative console with workflows for managing channels and packages, creating installers, and other distinct administrator tasks
- Added ability to mirror pip packages from PyPI repository
- Added ability to define custom hardware resource profiles based on CPU, RAM, and GPU for user sessions and deployments
- Added support for GPU worker nodes that can be defined in resource profiles
- Added ability to explicitly install different types of master nodes for high availability
- Added ability to specify NFS file shares that users can access within sessions and deployments
- Significantly reduced the amount of time required for backup/restore operations
- Added channel and package management tasks to UI, including downloading/uploading packages, creating/sharing channels, and more
- Anaconda Livy is now included in the Anaconda Enterprise installer to enable remote Spark connectivity
- All network traffic for services is now routed on standard HTTPS port 443, which reduces the number of external ports that need to be configured and accessed by end users
- Notebook/editor sessions are now accessed via subdomains for security and isolation
- Reworked documentation for administrator workflows, including managing cluster resources, configuring authentication, generating custom installers, and more
- Reduced verbosity of console output from `anaconda-enterprise-cli`
- Suppressed superfluous database errors/warnings

User-facing changes

- Added support for selecting GPU hardware in project sessions and deployments, to accelerate model training and other computations with GPU-enabled packages
- Added ability to select custom hardware resource profiles based on CPU, RAM, and GPU for individual sessions and deployments
- Added support for scheduled and batch jobs, which can be used for recurring tasks such as model training or ETL pipelines
- Added support for connecting to external Git repositories in a project session or deployment using account-wide credentials (SSH keys or API tokens)
- New, responsive user interface, redesigned for data science workflows
- Added ability to share deployments with unauthenticated users outside of Anaconda Enterprise
- Changed the default editor in project sessions to Jupyter Notebooks (formerly JupyterLab)
- Added ability to specify default editor on a per-project basis, including Jupyter Notebooks and JupyterLab
- Added ability to work with data in mounted NFS file shares within sessions and deployments
- Added ability to export/download projects from Anaconda Enterprise to local machine
- Added package and channel management tasks to UI, including uploading/downloading packages, creating/sharing channels, and more

- Reworked documentation for data science workflows, including working with projects/deployments/packages, using project templates, machine learning workflows, and more
- Added ability to use plotting/Javascript libraries in JupyterLab
- Added ability to force delete a project with running sessions, shared collaborators, etc.
- Improved messaging when a session or deployment cannot be scheduled due to limited cluster resources
- The last modified date/time for projects now accounts for commits to the project
- Unique names are now enforced for projects and deployments
- Fixed bug in which project creator role was not being enforced

Backend improvements (non-visible changes)

- Updated to Kubernetes 1.9.6
 - Added RHEL/CentOS 7.5 to supported platforms
 - Added support for SELinux passive mode
 - Anaconda Enterprise now uses the Helm package manager to manage and upgrade releases
 - New version (v2) of backend APIs with more comprehensive information around projects, deployments, packages, channels, credentials and more
 - Fixed various bugs related to custom Anaconda installer builds
 - Fixed issue with `kube-router` and a `CrashLoopBackOff` error
-

5.2.10 Anaconda Enterprise 5.1.3

Released: June 4, 2018

Backend improvements (non-visible changes)

- Fixed issue when generating custom Anaconda installers that contain packages with duplicate files
 - Fixed multiple issues related to memory errors, file size limits, and network transfer limits that affected the generation of large custom Anaconda installers
 - Improved logging when generating custom Anaconda installers
-

5.2.11 Anaconda Enterprise 5.1.2

Released: March 16, 2018

Administrator-facing changes

- Fixed issue with image/version tags when upgrading AE

Backend improvements (non-visible changes)

- Updated to Kubernetes 1.7.14
-

5.2.12 Anaconda Enterprise 5.1.1

Released: March 12, 2018

Administrator-facing changes

- Ability to specify custom UID for service account at install-time (default UID: 1000)
- Added pre-flight checks for kernel modules, kernel settings, and filesystem options when installing or adding nodes
- Improved initial startup time of project creation, sessions, and deployments after installation. Note that all services will be in the `ContainerCreating` state for 5 to 10 minutes while all AE images are being pre-pulled, after which the AE user interface will become available.
- Improved upgrade process to automatically handle upgrading AE core services
- Improved consistency between GUI- and CLI-based installation paths
- Improved security and isolation between internal database from user sessions and deployments
- Added capability to configure a custom trust store and LDAPS certificate validation
- Simplified installer packaging using a single tarball and consistent naming
- Updated documentation for system requirements, including XFS filesystem requirements and kernel modules/settings
- Updated documentation for mirroring packages from channels
- Added documentation for configuring AE to point to online Anaconda repositories
- Added documentation for securing the internal database
- Added documentation for configuring RBAC, role mapping, and access control
- Added documentation for LDAP federation and identity management
- Improved documentation for backup/restore process
- Fixed issue when deleting related versions of custom Anaconda parcels
- Added command to remove channel permissions
- Fixed issue related to Ops Center user creation in post-install configuration
- Silenced warnings when using `verify_ssl` setting with `anaconda-enterprise-cli`
- Fixed issue related to default admin role (`ae-admin`)
- Fixed issue when generating TLS/SSL certificates with FQDNs greater than 64 characters
- Fixed issue when using special characters with AE Ops Center accounts/passwords
- Fixed bug related to Administrator Console link in menu

User-facing changes

- Improvements to collaborative workflow: Added notification when collaborators make changes to a project, ability to pull changes into a project, and ability to resolve conflicting changes when saving or pulling changes into a project.
- Additional documentation and examples for connecting to remote data and compute sources: Spark, Hive, Impala, and HDFS
- Optimized startup time for Spark and SAS project templates

- Improved initial startup time of project creation, sessions, and deployments by pre-pulling images after installation.
 - Increased upload limit of projects from 100 MB to 1 GB
 - Added capability to `sudo yum install` system packages from within project sessions
 - Fixed issue when uploading projects that caused them to fail during partial import
 - Fixed R kernel in R project template
 - Fixed issue when loading `sparklyr` in Spark Project
 - Fixed issue related to displaying kernel names and Spark project icons
 - Improved performance when rendering large number of projects, packages, etc.
 - Improved rendering of long version names in environments and projects
 - Render full names when sharing projects and deployments with collaborators
 - Fixed issue when sorting collaborators and package versions
 - Fixed issue when saving new environments
 - Fixed issues when viewing installer logs in IE 11 and Safari
-

5.2.13 Anaconda Enterprise 5.1.0

Released: January 19, 2018

Administrator-facing changes

- New post-installation administration GUI with automated configuration of TLS/SSL certificates, administrator account, and DNS/FQDN settings; significantly reduces manual steps required during post-installation configuration process
- New functionality for administrators to generate custom Anaconda installers, parcels for Cloudera CDH, and management packs for Hortonworks HDP
- Improved backup and restore process with included scripts
- Switched from groups to roles for role-based access control (RBAC) for Administrator and superuser access to AE services
- Clarified system requirements related to system modules and IOPS in documentation
- Added ability to specify fractional CPUs/cores in global container resource limits
- Fixed consistency of TLS/SSL certificate names in configuration and during creation of self-signed certificates
- Changed use of `verify_ssl` to `ssl_verify` throughout AE CLI for consistency with `conda`
- Fixed configuration issue with licenses, including field names and online/offline licensing documentation

User changes

- Updated default project environments to Anaconda Distribution 5.0.1
- Improved configuration and documentation on using Sparkmagic and Livy with Kerberos to connect to remote Spark clusters
- Fixed R environment used in sample projects and project template
- Fixed UI rendering issue on package detail view of channels, downloads, and versions

- Fix multiple browser compatibility issues with Microsoft Edge and Internet Explorer 11
- Fixed multiple UI issues with Anaconda Project JupyterLab extension

Backend improvements (non-visible changes)

- Updated to Kubernetes 1.7.12
- Updated to conda 4.3.32
- Added SUSE 12 SP2/SP3, and RHEL/CentOS 7.4 to supported platform matrix
- Implemented TLS 1.2 as default TLS protocol; added support for configurable TLS protocol versions and ciphers
- Fixed default superuser roles for repository service, which is used for initial/internal package configuration step
- Implemented secure flag attribute on all session cookies containing session tokens
- Fixed issue during upgrade process that failed to vendor updated images
- Fixed `DiskNodeUnderPressure` and cluster stability issues
- Fixed Quality of Service (QoS) issue with core AE services on under-resourced nodes
- Fixed issue when using access token instead of ID token when fetching roles from authentication service
- Fixed issue with authentication proxy and session cookies

Known issues

- IE 11 compatibility issue when using Bokeh in notebooks (including sample projects)
 - IE 11 compatibility issue when downloading custom installers
-

5.2.14 Anaconda Enterprise 5.0.6

Released: November 9, 2017

5.2.15 Anaconda Enterprise 5.0.5

Released: November 7, 2017

5.2.16 Anaconda Enterprise 5.0.4

Released: September 12, 2017

5.2.17 Anaconda Enterprise 5.0.3

Released: August 31, 2017 (General Availability Release)

5.2.18 Anaconda Enterprise 5.0.2

Released: August 15, 2017 (Early Adopter Release)

5.2.19 Anaconda Enterprise 5.0.1

Released: March 8, 2017 (Early Adopter Release)

Features:

- Simplified, one-click deployment of data science projects and deployments, including live Python and R notebooks, interactive data visualizations and REST APIs.
- End-to-end secure workflows with SSL/TLS encryption.
- Seamlessly managed scalability of the entire platform
- Industry-grade productionization, encapsulation, and containerization of data science projects and applications.

5.3 Known issues

We are aware of the following issues using Anaconda Enterprise. If you're experiencing other unexpected behavior, consider checking our [Support Knowledge Base](#).

5.3.1 Unable to obtain Zeppelin credentials

After selecting **Credential** and clicking the question mark icon in the Zeppelin editor, the user should be redirected to Zeppelin documentation explaining the process for obtaining credentials. However, that link is broken.

Workaround

Rather than committing something sensitive in your code/repository through Zeppelin, create a [Kubernetes secret](#) in JSON format.

5.3.2 Process for installing the Anaconda Enterprise CLI doesn't work

The process of installing the Anaconda Enterprise CLI downgrades packages that are essential to the AE CLI, resulting in a conda env that won't work with the tool.

Workaround

Follow this process to create a working conda environment, and activate it:

```
conda create -n cli-test -c https://anaconda.example.com/repository/conda/anaconda-
↪enterprise anaconda-enterprise-cli git python=3.6 cas-mirror
conda activate cli-test
```

To access help for using the Anaconda Enterprise CLI, run `anaconda-enterprise-cli --help`.

5.3.3 Attempting to install new PyViz packages in JupyterLab results in error

The new PyViz libraries aren't compatible with the version of JupyterLab used in Anaconda Enterprise. For more information on PyViz compatibility, see https://github.com/pyviz/pyviz_comms#compatibility.

Workaround

Open the project in Jupyter Notebook.

5.3.4 Unable to download files when running JupyterLab in Chrome browser

If you attempt to download a file from within a JupyterLab project running on Chrome, you may see a `Failed/Forbidden` error, preventing you from being unable to download the file.

Workaround

Open the project in Jupyter Notebook or another supported browser, such as Firefox or Safari, and download the file.

5.3.5 Unexpected metadata in a package breaks AE channel

The `cspice` and `spiceypy` packages mirrored from conda-forge include incompatible metadata, which causes a `channeldata.json` build failure, and makes the entire channel inaccessible.

Workaround

Remove these packages from the AE channel, or update your conda-forge mirror to pull in the latest packages.

5.3.6 Custom conda configuration file may be overwritten

If you add a custom `.condarc` file to your project using the `anaconda-enterprise-cli spark-config` command, it may get overwritten with the default config options when you deploy the project.

Workaround

Place the `.condarc` file in a directory other than your home directory (`/opt/continuum/.condarc`).

Note that the conda config settings are loaded from all of the files on the conda config search path. The config settings are merged together, with keys from higher priority files taking precedence over keys from lower priority files. If you need extra settings, start by adding the `.condarc` file to a lower priority file first and see if this works for you.

For more information on how directory locations are prioritized, see [this blog post](#).

Starting in Anaconda Enterprise 5.3.1, you can also *set global config variables via a config map*, as an alternative to using the AE CLI.

5.3.7 Incorrect information in command output

When running the `anaconda-enterprise-cli spark-config` command to *connect to a remote Hadoop Spark cluster from within a project*, the output says you need to specify the namespace by including `-n anaconda-enterprise`.

Workaround

You must omit `-n anaconda-enterprise` from the command, as AE is installed in the `default` namespace.

5.3.8 Error creating an environment immediately after installation

At least one project must exist on the platform before you can *create an environment*. If you attempt to create an environment first, the logs will say that the associated job is `running`, and the container isn't ready.

Workaround

Create a project first. The environment creation process will continue and successfully complete after a few minutes.

5.3.9 Cluster performance may degrade after extended use

The default limit for `max_user_watches` may be insufficient, and can be increased to improve cluster longevity.

Workaround

Run the following command *on each node in the cluster*, to help the cluster remain active:

```
sysctl -w fs.inotify.max_user_watches=1048576
```

To ensure this change persists across reboots, you'll also need to run the following command:

```
sudo echo -e "fs.inotify.max_user_watches = 1048576" > /etc/sysctl.d/10-fs.inotify.  
↪max_user_watches.conf
```

5.3.10 Invalid issuer URL causes library to get stuck in a sync loop

When using the Anaconda Enterprise Operations Center to create an OIDC Auth Connector, if you enter an invalid issuer url in the spec, the `go-oidc` library can get stuck in a sync loop. This will affect *all* connectors.

Workaround

On a single node cluster, you'll need to do the following shut down gravity:

1. Find the gravity services: `systemctl list-units | grep gravity`.

You will see output like this:

```
# systemctl list-units | grep gravity  
gravity__gravitational.io__planet-master__0.1.87-1714.service          loaded_  
↪active running  
    Auto-generated service for the gravitational.io/planet-master:0.1.87-1714_  
↪package  
gravity__gravitational.io__teleport__2.3.5.service                  loaded_  
↪active running  
    Auto-generated service for the gravitational.io/teleport:2.3.5 package
```

2. Shut down the teleport service:

```
systemctl stop gravity__gravitational.io__teleport__2.3.5.service
```

3. Shut down the planet-master service:

```
systemctl stop gravity__gravitational.io__planet-master__0.1.87-1714.service
```

On a multi-node cluster, you'll need to shut down gravity AND all gravity-site pods:

```
kubectl delete pods -n kube-system gravity-site-XXXXX
```

In both cases, you'll need to restart gravity services:

```
systemctl start gravity__gravitational.io__planet-master__0.1.87-1714.service  
systemctl start gravity__gravitational.io__teleport__2.3.5.service
```

5.3.11 GPU affinity setting reverts to default during upgrade

When upgrading Anaconda Enterprise from a version that supports the ability to reserve GPU nodes to a newer version (e.g., 5.2.x > 5.2.3), the `nodeAffinity` setting reverts to the default value, thus allowing CPU sessions and deployments to run on GPU nodes.

Workaround

If you had commented out the `nodeAffinity` section of the Config map in your previous installation, you'll need to do so again after completing the upgrade process. See [Setting resource limits](#) for more information.

5.3.12 Install and post-install problems

Failed installations

If an installation fails, you can view the failed logs as part of the support bundle in the failed installation UI.

After executing `sudo gravity enter` you can check `/var/log/messages` to troubleshoot a failed installation or these types of errors.

After executing `sudo gravity enter` you can run `journalctl` to look at logs to troubleshoot a failed installation or these types of errors:

```
journalctl -u gravity-234231kqjfefqpfh2.service
```

Note: Replace `gravity-234231kqjfefqpfh2.service` with the name of your gravity service.

You may see messages in `/var/log/messages` related to errors such as “etcd cluster is misconfigured” and “etcd has no leader” from one of the installation jobs, particularly `gravity-site`. This usually indicates that `etcd` needs more compute power, needs more space or is on a slow disk.

Anaconda Enterprise is very sensitive to disk latency, so we usually recommend using a better disk for `/var/lib/gravity` on target machines and/or putting `etcd` data on a separate disk. For example, you can mount `etcd` under `/var/lib/gravity/planet/etcd` on the hosts.

After a failed installation, you can [uninstall Anaconda Enterprise](#) and start over with a fresh installation.

Failed on pulling gravitational/rbac

If the node refuses to install and fails on pulling `gravitational/rbac`, create a new directory `TMPDIR` before installing and provide write access to user 1000.

“Cannot continue” error during install

This bug is caused by a previous failure of a kernel module check or other preflight check and subsequent attempt to reinstall.

Stop the install, make sure the preflight check failure is resolved, and restart the install again.

Problems during post-install or post-upgrade steps

Post-install and post-upgrade steps run as Kubernetes jobs. When they finish running, the pods used to run them are **not** removed. These and other stopped pods can be found using:

```
kubectl get pods -A
```

The logs in each of these three pods will be helpful for diagnosing issues in the following steps:

Pod	Issues in this step
ae-wagonwheel	post-install UI
install	installation step
postupdate	post-update steps

Post-install configuration doesn't complete

After completing the post-install steps, clicking **FINISH SETUP** may not close the screen, and prevent you from continuing.

You can complete the process by running the following commands within gravity.

To determine the site name:

```
SITE_NAME=$(gravity status --output=json | jq '.cluster.token.site_domain' -r)
```

To complete the post-install process:

```
gravity --insecure site complete
```

Re-starting the post-install configuration

In order to reinitialize the post-install configuration UI—to regenerate temporary (self-signed) SSL certificates or reconfigure the platform based on your domain name—you must re-create and re-expose the service on a new port.

First, export the deployment's resource manifest:

```
helm template --name anaconda-enterprise /var/lib/gravity/local/packages/unpacked/  
↪gravitational.io/AnacondaEnterprise/5.X.X/resources/Anaconda-Enterprise/ -x /var/  
↪lib/gravity/local/packages/unpacked/gravitational.io/AnacondaEnterprise/5.X.X/  
↪resources/Anaconda-Enterprise/templates/wagonwheel.yaml > wagon.yaml
```

Edit `wagon.yaml`, replacing `image: ae-wagonwheel:5.X.X` with `image: leader.telekube.local:5000/ae-wagonwheel:5.X.X`

Then recreate the `ae-wagonwheel` deployment using the updated YAML file:

```
kubectl create -f /var/lib/gravity/site/packages/unpacked/gravitational.io/  
↪AnacondaEnterprise/5.X.X/resources/wagon.yaml -n kube-system
```

NOTE: Replace 5.X.X with your actual version number.

To ensure the deployment is running in the system namespace, execute `sudo gravity enter` and run:

```
kubectl get deploy -n kube-system
```

One of these should be `ae-wagonwheel`, the post-install configuration UI. To make this visible to the outside world, run:

```
kubectl expose deploy ae-wagonwheel --port=8000 --type=NodePort --name=post-install -  
↪n kube-system
```

This will run the UI on a new port, allocated by Kubernetes, under the name `post-install`.

To find out which port it is listening under, run:

```
kubectl get svc -n kube-system | grep post-install
```

Then navigate to `http://<your domain>:<this port>` to access the *post-install UI*.

5.3.13 Kernel parameters may be overwritten and cause networking errors

If networking starts to fail in Anaconda Enterprise, it may be because a kernel parameter related to networking was inadvertently overwritten.

Workaround

On the master node running AE, run `gravity status` and verify that all kernel parameters are set correctly. If the Status for a particular parameter is degraded, follow [the instructions here](#) to reset the kernel parameter.

5.3.14 Removing collaborator from project with open session generates error

If you remove a collaborator from a project while they have a session open for that project, they might see a 500 Internal Server Error message.

Workaround

Add the user as a collaborator to the project, have them stop their notebook session, then remove them as a collaborator. For more information, see [how to share a project](#).

To prevent collaborators from seeing this error, ask them to close their running session before you remove them from the project.

Affected versions

5.2.x

5.3.15 AE auth pod throws OutOfMemory Error

If you see an exception similar to the following, Anaconda Enterprise has exceeded the maximum heap size for the JVM:

```
Exception: java.lang.OutOfMemoryError thrown from the UncaughtExceptionHandler in
↳thread "default task-248"
2018-08-29 23:13:26.327 UTC ERROR    XNIO0001007: A channel event listener threw an
↳exception: java.lang.OutOfMemoryError: Java heap space (default I/O-36) [org.xnio.
↳listener]
2018-08-29 23:12:32.823 UTC ERROR    UT005023: Exception handling request to /auth/
↳realms/AnacondaPlatform/protocol/openid-connect/token: java.lang.OutOfMemoryError:
↳Java heap space (default task-86) [io.undertow.request]
2018-08-29 23:13:01.353 UTC ERROR    XNIO0001007: A channel event listener threw an
↳exception: java.lang.OutOfMemoryError: Java heap space
```

Workaround

Increase the JVM max heap size by doing the following:

1. Open the `anaconda-enterprise-ap-auth` deployment spec by running the following command in a terminal:

```
$ kubectl edit deploy anaconda-enterprise-ap-auth
```

2. Increase the value for `JAVA_OPTS` (example below):

```
spec:
  containers:
    - args:
      - cp /standalone-config/standalone.xml /opt/jboss/keycloak/standalone/
↳configuration/
```

(continues on next page)

(continued from previous page)

```

    && /opt/jboss/keycloak/bin/standalone.sh -Dkeycloak.migration.action=import
    -Dkeycloak.migration.provider=singleFile -Dkeycloak.migration.file=/etc/
    ↪secrets/keycloak/keycloak.json
    -Dkeycloak.migration.strategy=IGNORE_EXISTING -b 0.0.0.0
  command:
  - /bin/sh
  - -c
  env:
  - name: DB_URL
    value: anaconda-enterprise-postgres:5432
  - name: SERVICE_MIGRATE
    value: auth_quick_migrate
  - name: SERVICE_LAUNCH
    value: auth_quick_launch
  - name: JAVA_OPTS
    value: -Xms64m -Xmx2048m -XX:MetaspaceSize=96M -XX:MaxMetaspaceSize=256m

```

Affected versions

5.2.1

5.3.16 Fetch changes behavior in Apache Zeppelin may not be obvious to new users

A Fetch changes notification appears, but the changes do not get applied to the editor. This is how Zeppelin works, but users unfamiliar with the editor may find it confusing.

If a collaborator makes changes to a notebook that's also open by another user, the user needs to pull the changes that the collaborator made AND click the small reload arrows to refresh their notebook with the changes (see below).

**Affected versions**

5.2.2

5.3.17 Apache Zeppelin can't locate conflicted files or non-Zeppelin notebook files

If you need to access files other than Apache Zeppelin notebooks within a project, you can use the %sh interpreter from within a Zeppelin notebook to work with files via bash commands, or use the **Settings** tab to change the default editor to Jupyter Notebooks or JupyterLab and use the file browser or terminal.

Affected versions

5.2.2

5.3.18 Create and Installer buttons are not visible on Channels page

When the Channels page is viewed initially, the Create and Installers buttons are not visible on the top right section of the screen. This prevents the user from creating channels or viewing a list of installers.

Workaround

To make the Create and Installer buttons visible on the Channels page, perform one of the following steps:

- Click on the top-level Channels navigation link again when viewing the Channels page
- Click on a specific channel to view its detail page, then return to the Channels page

Affected versions

5.2.1

5.3.19 Updating a package from the Anaconda metapackage

When updating a package dependency of a project, if that dependency is part of the Anaconda metapackage the package will be installed once but a subsequent `anaconda-project` call will uninstall the upgraded package.

Workaround

When updating a package dependency remove the `anaconda` metapackage from the list of dependencies at the same time add the new version of the dependency that you want to update.

Affected versions

5.1.0, 5.1.1, 5.1.2, 5.1.3

5.3.20 File size limit when uploading files

Unable to upload new files inside of a project that are larger than the current restrictions:

- The limit of file uploads in JupyterLab is 15 MB

Affected versions

5.1.0, 5.1.1, 5.1.2, 5.1.3, 5.2.0, 5.2.1, 5.2.2, 5.2.3

5.3.21 IE 11 compatibility issue when using Bokeh in projects (including sample projects)

Bokeh plots and applications have had a number of issues with Internet Explorer 11, which typically result in the user seeing a blank screen.

Workaround

Upgrade to the latest version of Bokeh available. On Anaconda 4.4 the latest is 0.12.7. On Anaconda 5.0 the latest version of Bokeh is 0.12.13. If you are still having issues, consult the Bokeh team or support.

Affected versions

5.1.0, 5.1.1, 5.1.2, 5.1.3

5.3.22 IE 11 compatibility issue when downloading custom Anaconda installers

Unable to download a custom Anaconda installer from the browser when using Internet Explorer 11 on Windows 7. Attempting to download a custom installer with this setup will result in an error that “This page can’t be displayed”.

Workaround

Custom installers can be downloaded by refreshing the page with the error message, clicking the “Fix Connection Error” button, or using a different browser.

Affected versions

5.1.0, 5.1.1, 5.1.2, 5.1.3

5.3.23 Project names over 40 characters may prevent JupyterLab launch

If a project name is more than 40 characters long, launching the project in JupyterLab may fail.

Workaround

Rename the project to a name less than 40 characters long and launch the project in JupyterLab again.

Affected versions

5.1.1, 5.1.2, 5.1.3

5.3.24 Long-running jobs may falsely report failure

If a job (such as an installer, parcel, or management pack build) runs for more than 10 minutes, the UI may falsely report that the job has failed. The apparent job failure occurs because the session/access token in the UI has expired.

However, the job will continue to run in the background, the job run history will indicate a status of “running job” or “finished job”, and the job logs will be accessible.

Workaround

To prevent false reports of failed jobs from occurring in the UI, you can extend the access token lifespan (default: 10 minutes).

To extend the access token lifespan, log in to the Anaconda Enterprise Authentication Center, navigate to Realm Settings > Tokens, then increase the Access Token Lifespan to be at least as long as the jobs being run (e.g., 30 minutes).

Affected versions

5.1.0, 5.1.1, 5.1.2, 5.1.3

5.3.25 New Notebook not found on IE11

On Internet Explorer 11, creating a new Notebook in a Classic Notebook editing session may produce the error “404: Not Found”. This is an artifact of the way that Internet Explorer 11 locates files.

Workaround

If you see this error, click “Back to project”, then click “Return to Session”. This refreshes the file list and allows IE11 to find the file. You should see the new notebook in the file list. Click on it to open the notebook.

Affected versions

5.0.4, 5.0.5

5.3.26 Disk pressure errors on AWS

If your Anaconda Enterprise instance is on Amazon Web Services (AWS), overloading the system with reads and writes to the directory `/opt/anaconda` can cause disk pressure errors, which may result in the following:

- Slow project starts.
- Project failures.
- Slow deployment completions.
- Deployment failures.

If you see these problems, check the logs to verify whether disk pressure is the cause:

1. To list all nodes, run:

```
kubectl get node
```

2. Identify which node is experiencing issues, then run the following command against it, to view the log for that node:

```
kubectl describe node <master-node-name>
```

If there is disk pressure, the log will display an error message similar to the following:

```
Events:
  Type            Reason              Age             From              Message
  ----            -
  Normal          NodeHasDiskPressure  9m              kubelet, 172.31.63.118 Node 172.31.63.118 status is now: NodeHasDiskPressure
  Warning         ImageFailed         4m (x3858 over 18d) kubelet, 172.31.63.118 (combined from similar events): wanted to free 22198091468 bytes
  log used by running container c90372779417
  Warning         EvictionThresholdMet 2s (x2 over 2d)  kubelet, 172.31.63.118 Attempting to reclaim nodefs
```

Workaround

To relieve disk pressure, you can add disks to the instance by adding another Elastic Block Store (EBS) volume. If the disk pressure is being caused by a back up, you can move the backed up file somewhere else (e.g., to an NFS mount). See [Backing up and restoring AE](#) for more information.

To add disks to the instance by adding another Elastic Block Store (EBS) volume.

1. Open the AWS console and add a new EBS volume provisioned to 3000 IOPS. A typical disk size is 500 GB.
2. Attach the volume to your AE 5 master.
3. To find your new disk's name run `fdisk -l`. Our example disk's name is `/dev/nvme1n1`. In the rest of the commands on this page, replace `/dev/nvme1n1` with your disk's name.
4. Format the new disk: `fdisk /dev/nvme1n1`

To create a new partition, at the first prompt press `n` and then the return key.

Accept all default settings.

To write the changes, press `w` and then the return key. This will take a few minutes.

5. To find your new partition's name, examine the output of the last command. If the name is not there, run `fdisk -l` again to find it.

Our example partition's name is `/dev/nvme1n1p1`. In the rest of the commands on this page, replace `/dev/nvme1n1p1` with your partition's name.

6. Make a file system on the new partition: `mkfs /dev/nvme1n1p1`

7. Make a temporary directory to capture the contents of /opt/anaconda: `mkdir /opt/aetmp`
8. Mount the new partition to /opt/aetmp: `mount /dev/nvme1n1p1 /opt/aetmp`
9. Shut down the Kubernetes system.

Find the gravity services: `systemctl list-units | grep gravity`

You will see output like this:

```
# systemctl list-units | grep gravity
gravity__gravitational.io__planet-master__0.1.87-1714.service      loaded_
↳active running
    Auto-generated service for the gravitational.io/planet-master:0.1.87-1714_
↳package
gravity__gravitational.io__teleport__2.3.5.service                loaded_
↳active running
    Auto-generated service for the gravitational.io/teleport:2.3.5 package
```

Shut down the teleport service: `systemctl stop gravity__gravitational.io__teleport__2.3.5.service`

Shut down the planet-master service: `systemctl stop gravity__gravitational.io__planet-master__0.1.87-1714.service`

10. Copy everything from /opt/anaconda to /opt/aetmp: `rsync -vpoa /opt/anaconda/* /opt/aetmp`
11. Include the new disk at the /opt/anaconda mount point by adding this line to your file systems table at /etc/fstab:

/dev/nvme1n1p1	/opt/anaconda	ext4	defaults	0 0
----------------	---------------	------	----------	-----

Use mixed spaces and tabs in this pattern: `/dev/nvme1n1p1<tab>/opt/anaconda<tab>ext4<tab>defaults<tab>0<space>0`

12. Move the old /opt/anaconda out of the way to /opt/anaconda-old: `mv /opt/anaconda /opt/anaconda-old`
- If you're certain the `rsync` was successful, you may instead delete /opt/anaconda: `rm -r /opt/anaconda`

13. Unmount the new disk from the /opt/aetmp mount point: `umount /opt/aetmp`
14. Make a new /opt/anaconda directory: `mkdir /opt/anaconda`
15. Mount all the disks defined in fstab: `mount -a`
16. Restart the gravity services:

```
systemctl start gravity__gravitational.io__planet-master__0.1.87-1714.service
systemctl start gravity__gravitational.io__teleport__2.3.5.service
```

5.3.27 Disk pressure error during backup

If a disk pressure error occurs *while backing up your configuration*, the amount of data being backed up has likely exceeded the amount of space available to store the backup files. This triggers the Kubernetes eviction policy defined in the `kubelet` startup parameter and causes the backup to fail.

To check your eviction policy, run the following commands *on the master node*:

```
sudo gravity enter
systemctl status | grep "/usr/bin/kubelet"
```

Workaround

Restart the backup process, and specify a location with sufficient space (e.g., an NFS mount) to store the backup files. See [Backing up and restoring AE](#) for more information.

5.3.28 General diagnostic and troubleshooting steps

Entering Anaconda Enterprise environment

To enter the Anaconda Enterprise environment and gain access to `kubectl` and other commands within Anaconda Enterprise, use the command:

```
sudo gravity enter
```

Moving files and data

Occasionally you may need to move files and data from the host machine to the Anaconda Enterprise environment. If so, there are two *shared mounts* to pass data back and forth between the two environments:

- host: `/opt/anaconda/` -> AE environment: `/opt/anaconda/`
- host: `/var/lib/gravity/planet/share` -> AE environment: `/ext/share`

If data is written to either of the locations, that data will be available on both the host machine and within the Anaconda Enterprise environment

Debugging

AWS Traffic needs to handle the public IPs and ports. You should either use a canonical security group with the proper ports opened or manually add the specific ports listed in [Network Requirements](#).

Problems during air gap project migration

The command `anaconda-project lock` over-specifies the channel list resulting in a conda bug where it adds defaults from the internet to the list of channels.

Solution:

Add to the `.condarc`: “`default_channels`”. This way, when conda adds “defaults” to the command it is adding the internal repo server and not the `repo.continuum.io` URLs.

EXAMPLE:

```
default_channels:
- anaconda
channels:
- our-internal
- out-partners
- rdkit
- bioconda
- defaults
- r-channel
- conda-forge
channel_alias: https://:8086/conda
auto_update_conda: false
ssl_verify: /etc/ssl/certs/ca.2048.cer
```

LDAP error in ap-auth

```
[LDAP: error code 12 - Unavailable Critical Extension]; remaining name  
'dc=acme, dc=com'
```

This error can be caused when pagination is turned on. Pagination is a server side extension and is not supported by some LDAP servers, notably the Sun Directory server.

Session startup errors

If you need to troubleshoot session startup, you can use a terminal to view the session startup logs. When session startup begins the output of the `anaconda-project prepare` command is written to `/opt/continuum/Preparing`, and when the command completes the log is moved to `/opt/continuum/prepare.log`.

5.4 Frequently asked questions

5.4.1 General

When was the general availability release of Anaconda Enterprise v5?

Our GA release was August 31, 2017 (version 5.0.3). Our most recent version was released April 15, 2020 (version 5.4.1).

Which notebooks or editors does Anaconda Enterprise support?

Anaconda Enterprise supports the use of Jupyter Notebooks and JupyterLab, which are the most popular integrated data science environments for working with Python and R notebooks. In version 5.2.2 we added support for Apache Zeppelin, a web-based notebook that enables data-driven, interactive data analytics and collaborative documents with interpreters for Python, R, Spark, Hive, HDFS, SQL, and more.

Can I deploy multiple data science applications to Anaconda Enterprise?

Yes, you can deploy multiple data science applications and languages across an Anaconda Enterprise cluster. Each data science application runs in a secure and isolated environment with all of the dependencies from Anaconda that it requires.

A single node can run multiple applications based on the amount of compute resources (CPU and RAM) available on a given node. Anaconda Enterprise handles all of the resource allocation and application scheduling for you.

Does Anaconda Enterprise support high availability deployments?

Partially. Some of the Anaconda Enterprise services and user-deployed apps will be automatically configured when installed to three or more nodes. Anaconda Enterprise provides several automatic mechanisms for fault tolerance and service continuity, including automatic restarts, health checks, and service migration.

For more information, see [Fault tolerance in Anaconda Enterprise](#).

Which identity management and authentication protocols does Anaconda Enterprise support?

Anaconda Enterprise comes with out-of-the-box support for the following:

- LDAP / AD
- SAML
- Kerberos

For more information, see [Connecting to external identity providers](#).

Does Anaconda Enterprise support two-factor authentication (including one-time passwords)?

Yes, Anaconda Enterprise supports single sign-on (SSO) and two-factor authentication (2FA) using FreeOTP, Google Authenticator or Google Authenticator compatible 2FA.

You can configure one-time password policies in Anaconda Enterprise by navigating to the authentication center and clicking on Authentication and then OTP Policy.

5.4.2 System requirements

What operating systems are supported for Anaconda Enterprise?

Please see [operating system requirements](#).

Note: Linux distributions other than those listed in the documentation can be supported on request.

What are the minimum system requirements for Anaconda Enterprise nodes?

Please see [system requirements](#).

Which browsers are supported for Anaconda Enterprise?

Please see [browser requirements](#).

Does Anaconda Enterprise come with a version control system?

Yes, Anaconda Enterprise includes an internal Git server, which allows users to save and commit versions of their projects.

Can Anaconda Enterprise integrate with my own Git server?

Yes, as described in [Connecting to an external version control repository](#).

5.4.3 Installation

How do I install Anaconda Enterprise?

The Anaconda Enterprise installer is a single tarball that includes Docker, Kubernetes, system dependencies, and all of the components and images necessary to run Anaconda Enterprise. The system administrator runs one command on each node.

Can Anaconda Enterprise be installed on-premises?

Yes, including airgapped environments.

Can Anaconda Enterprise be installed on cloud environments?

Yes, including Amazon AWS, Microsoft Azure, and Google Cloud Platform.

Does Anaconda Enterprise support air gapped (off-line) environments?

Yes, the Anaconda Enterprise installer includes Docker, Kubernetes, system dependencies, and all of the components and images necessary to run Anaconda Enterprise on-premises or on a private cloud, with or without internet connectivity. We can deliver the installer to you on a USB drive.

Can I build Docker images for the install of Anaconda Enterprise?

No. The installation of Anaconda Enterprise is supported only by using the single-file installer. The Anaconda Enterprise installer includes Docker, Kubernetes, system dependencies, and all of the components and images necessary for Anaconda Enterprise.

Can I install Anaconda Enterprise on my own instance of Kubernetes?

No. The Anaconda Enterprise installer already includes Kubernetes.

Can I get the AE installer packaged as a virtual machine (VM), Amazon Machine Image (AMI) or other installation package?

No. The installation of Anaconda Enterprise is supported only by using the single-file installer.

Which ports are externally accessible from Anaconda Enterprise?

Please see [network requirements](#).

Can I use Anaconda Enterprise to connect to my Hadoop/Spark cluster?

Yes. Anaconda Enterprise supports connectivity from notebooks to local or remote Spark clusters by using the Sparkmagic client and a Livy REST API server. Anaconda Enterprise provides Sparkmagic, which includes Spark, PySpark, and SparkR notebook kernels for deployment.

How can I manage Anaconda packages on my Hadoop/Spark cluster?

An administrator can generate custom Anaconda parcels for Cloudera CDH or custom Anaconda management packs for Hortonworks HDP using Anaconda Enterprise. A data scientist can use these Anaconda libraries from a notebook as part of a Spark job.

On how many nodes can I install Anaconda Enterprise?

You can install Anaconda Enterprise in the following configurations during the initial installation:

- One node (one master node)
- Two nodes (one master node, one worker node)
- Three nodes (one master node, two worker nodes)
- Four nodes (one master node, three worker nodes)

After the initial installation, you can add or remove worker nodes from the Anaconda Enterprise cluster at any time.

One node serves as the master node and writes storage to disk, and the other nodes serve as worker nodes. Anaconda Enterprise services and user-deployed applications run seamlessly on the master and worker nodes.

Can I generate certificates manually?

Yes, if automatic TLS/SSL certificate generation fails for any reason, you can generate the certificates manually. Follow these steps:

1. Generate self-signed temporary certificates. On the master node, run:

```
cd path/to/Anaconda/Enterprise/unpacked/installer
cd DIY-SSL-CA
bash create_noprompt.sh DESIRED_FQDN
cp out/DESIRED_FQDN/secret.yaml /var/lib/gravity/planet/share/secrets.yaml
```

Replace `DESIRED_FQDN` with the fully-qualified domain of the cluster to which you are installing Anaconda Enterprise.

Saving this file as `/var/lib/gravity/planet/share/secrets.yaml` on the Anaconda Enterprise master node makes it accessible as `/ext/share/secrets.yaml` within the Anaconda Enterprise environment which can be accessed with the command `sudo gravity enter`.

2. Update the `certs` secret

Replace the built-in `certs` secret with the contents of `secrets.yaml`. Enter the Anaconda Enterprise environment and run these commands:

```
$ kubectl delete secrets certs
secret "certs" deleted
$ kubectl create -f /ext/share/secrets.yaml
secret "certs" created
```

5.4.4 GPU Support

How can I make GPUs available to my team of data scientists?

If your data science team plans to use version 5.2 of the Anaconda Enterprise AI enablement platform, here are a few approaches to consider when planning your GPU cluster:

- *Build a dedicated GPU-only cluster.*

If GPUs will be used by specific teams only, creating a separate cluster allows you to more carefully control GPU access.

- *Build a heterogeneous cluster.*

Not all projects require GPUs, so a cluster containing a mix of worker nodes—with and without GPUs—can serve a variety of use cases in a cost-effective way.

- *Add GPU nodes to an existing cluster.*

If your team’s resource requirements aren’t clearly defined, you can start with a CPU-only cluster, and add GPU nodes to create a heterogeneous cluster when the need arises.

Anaconda Enterprise supports heterogeneous clusters by allowing you to create different “resource profiles” for projects. Each resource profile describes the number of CPU cores, the amount of memory, and the number of GPUs the project needs. Administrators typically will create “Regular”, “Large”, and “Large + GPU” resource profiles for users to select from when running their project. If a project requires a GPU, AE will run it on only those cluster nodes with an available GPU.

What software is GPU accelerated?

Anaconda provides a number of GPU-accelerated packages for data science. For deep learning, these include:

- Keras (`keras-gpu`)
- TensorFlow (`tensorflow-gpu`)
- Caffe (`caffe-gpu`)
- PyTorch (`pytorch`)
- MXNet (`mxnet-gpu`)

For boosted decision tree models:

- XGBoost (`py-xgboost-gpu`)

For more general array programming, custom algorithm development, and simulations:

- CuPy (`cupy`)
- Numba (`numba`)

Note: Unless a package has been specifically optimized for GPUs (by the authors) and built by Anaconda with GPU support, it will not be GPU-accelerated, even if the hardware is present.

What hardware does each of my cluster nodes require?

Anaconda recommends installing Anaconda Enterprise in a cluster configuration. Each installation should have an odd number of master nodes, and we recommend at least one worker node. The master node runs all Anaconda Enterprise core services and does not need a GPU.

Using EC2 instances, a *minimal configuration* is one master node running on a `m4.4xlarge` instance and one GPU worker node running on a `p3.2xlarge` instance. More users will require more worker nodes—and possibly a mix of CPU and GPU worker nodes.

See [Installation requirements](#) for the baseline hardware requirements for Anaconda Enterprise.

How many GPUs does my cluster need?

A best practice for machine learning is for each user to have exclusive use of their GPU(s) while their project is running. This ensures they have sufficient GPU memory available for training, and provides more consistent performance.

When an Anaconda Enterprise user launches a notebook session or deployment that requires GPUs, those resources are reserved for as long as the project is running. When the notebook session or deployment is stopped, the GPUs are returned to the available pool for another user to claim.

The number of GPUs required in the cluster can therefore be determined by the number of concurrently running notebook sessions and deployments that are expected. Adding nodes to an Anaconda Enterprise cluster is straightforward, so organizations can start with a conservative number of GPUs and grow as demand increases.

To get more out of your GPU resources, Anaconda Enterprise supports scheduling and running unattended jobs. This enables you to execute periodic retraining tasks—or other resource-intensive tasks—after regular business hours, or at times GPUs would otherwise be idle.

What kind of GPUs should I use?

Although the Anaconda Distribution supports a wide range of NVIDIA GPUs, enterprise deployments for data science teams developing models should use one of the following GPUs:

- Tesla V100 (recommended)
- Tesla P100 (adequate)

Can I mix GPU models in one cluster?

Kubernetes cannot currently distinguish between different GPU models in the same cluster node, so Anaconda Enterprise requires all GPU-enabled nodes *within a given cluster* to have the same GPU model (for example, all Tesla V100). Different clusters (e.g., “production” and “development”) can use different GPU models, of course.

Can I use cloud GPUs?

Yes, Anaconda Enterprise 5.2 can be installed on cloud VMs with GPU support. Amazon Web Services (AWS), Google Cloud Platform, and Microsoft Azure all offer Tesla GPU options.

5.4.5 Anaconda Project

What operating systems and Python versions are supported for Anaconda Project?

Anaconda Project supports Windows, macOS and Linux, and tracks the latest Anaconda releases with Python 2.7, 3.5, 3.6, and 3.7.

How is encapsulation with Anaconda Project different from creating a workspace or project in Spyder, PyCharm, or other IDEs?

A workspace or project in an IDE is a directory of files on your desktop. Anaconda Project encapsulates those files, but also includes additional parameters to describe how to run a project with its dependencies. Anaconda Project is portable and allows users to run, share, and deploy applications across different operating systems.

What types of projects can I deploy?

Anaconda Project is very flexible and can deploy many types of projects with conda or pip dependencies. Deployable projects include:

- Notebooks (Python and R)
- Bokeh applications and dashboards
- REST APIs in Python and R (including machine learning scoring and predictions)
- Python and R scripts
- Third-party apps, web frameworks, and visualization tools such as Tensorboard, Flask, Falcon, deck.gl, plot.ly Dash, and more.

Any generic Python and R script or webapp can be configured to serve on port 8086, which will show the app in Anaconda Enterprise when deployed.

Does Anaconda Enterprise include Docker images for my data science projects?

Anaconda Enterprise includes data science application images for the editor and deployments. You can install additional packages in either environment using Anaconda Project. Anaconda Project includes the information required to reproduce the project environment with Anaconda, including Python, R, or any other conda package or pip dependencies.

After upgrading AE5 my projects no longer work

If you've upgraded to AE 5.4 and are getting package install errors you may need to re-write your `anaconda-project.yml` file.

If you were using modified template `anaconda-project.yml` files for Python 2.7, 3.5, or 3.6 it is best to leave the package list empty in the `env_specs` section. Then you should add your required packages and their versions to the global package list.

Here's an example using the Python 3.6 template `anaconda-project.yml` file from AE version 5.3.1 where the package list has been removed from the `env_specs` and the required packages added to the global list.

```
name: Python 3.6

description: A comprehensive project template that contains all of the packages_
↪available in the Anaconda Distribution v5.0.1 for Python 3.6. Get started with the_
↪most popular and powerful packages in data science.

channels: []
packages:
- python=3.6
- notebook
- pandas=0.25
- psycopg2
- holoviews

platforms:
- linux-64
- osx-64
- win-64

env_specs:
  anaconda50_py36:
    packages: []
    channels: []
```

5.4.6 Notebooks

Are the deployed, self-service notebooks read-only?

Yes, the deployed versions of self-service notebooks are read-only, but they can be executed by collaborators or viewers. Owners of the project that contain the notebooks can edit the notebook and deploy (or re-deploy) them.

What happens when other people run the notebook? Does it overwrite any file, if notebook is writing to a file?

A deployed, self-service notebook is read-only but can be executed by other collaborators or viewers. If multiple users are running a notebook that writes to a file, the file will be overwritten unless the notebook is configured to write data based on a username or other environment variable.

Can I define environment variables as part of my data science project?

Yes, Anaconda Project supports environment variables that can be defined when deploying a data science application. Only project collaborators can view or edit environment variables, and they cannot be accessed by viewers.

How are Anaconda Project and Anaconda Enterprise available?

Anaconda Project is free and open-source. Anaconda Enterprise is a commercial product.

Where can I find example projects for Anaconda Enterprise?

Sample projects are included as part of the Anaconda Enterprise installation, which include sample workflows and notebooks for Python and R such as financial modeling, natural language processing, machine learning models with REST APIs, interactive Bokeh applications and dashboards, image classification, and more.

The sample projects include examples with visualization tools (Bokeh, deck.gl), pandas, scipy, Shiny, Tensorflow, Tensorboard, xgboost, and many other libraries. Users can save the sample projects to their Anaconda Enterprise account or download the sample projects to their local machine.

Does Anaconda Enterprise support batch scoring with REST APIs?

Yes, Anaconda Enterprise can be used to deploy machine learning models with REST APIs (including Python and R) that can be queried for batch scoring workflows. The REST APIs can be made available to other users and accessed with an API token.

Does Anaconda Enterprise provide tools to help define and implement REST APIs?

Yes, a data scientist can basically create a model without much work for the API development. Anaconda Enterprise includes an API wrapper for Python frameworks that builds on top of existing web frameworks in Anaconda, making it easy to expose your existing data science models with minimal code. You can also deploy REST APIs using existing API frameworks for Python and R.

5.4.7 Help and training

Do you offer support for Anaconda Enterprise?

Yes, we offer full support with Anaconda Enterprise.

Do you offer training for Anaconda Enterprise?

Yes, we offer product training for collaborative, end-to-end data science workflows with Anaconda Enterprise.

Do you have a question not answered here?

Please [contact us](#) for more information.